

SONY

CATALYST EDIT

User Manual

Revised Wednesday, October 4, 2023

XDCAM, XDCAM EX, XAVC, XAVC S, NXCAM, SxS and Professional Disc are trademarks of Sony Corporation.

Avid and DNxHD are trademarks or registered trademarks of Avid Technology, Inc. or its subsidiaries in the United States and/or other countries.

All other trademarks or registered trademarks are the property of their respective owners in the United States and other countries and regions. For more information, see <https://www.sonycreativesoftware.com/licensenotices>

Sony Corporation may have patents, patent applications, trademarks, copyrights, or other intellectual property rights covering subject matter in this document. Except as expressly provided in any written license agreement from Sony Corporation, the furnishing of this document does not give you any license to these patents, trademarks, copyrights, or other intellectual property.

Sony Creative Software Inc.

1 S.Pinckney St.

Suite 520

Madison, WI 53703

USA

The information contained in this manual is subject to change without notice and does not represent a guarantee or commitment on behalf of Sony Creative Software Inc. in any way. All updates or additional information relating to the contents of this manual will be posted on the Sony Creative Software Inc. Web site, located at <https://www.sonycreativesoftware.com>. The software is provided to you under the terms of the End User License Agreement and Software Privacy Policy, and must be used and/or copied in accordance therewith. Copying or distributing the software except as expressly described in the End User License Agreement is strictly prohibited. No part of this manual may be reproduced or transmitted in any form or for any purpose without the express written consent of Sony Creative Software Inc.

Copyright © 2023. Sony Creative Software Inc.

Program Copyright © 2023. Sony Creative Software Inc. All rights reserved.

Table of Contents

Table of Contents	3
Introduction	7
The Catalyst Edit window	7
Working with projects	11
Creating projects	11
Opening projects	11
Relinking project media	13
Saving projects	13
Using the Timeline Inspector	14
Sharing projects	18
Rendering projects	20
Exporting projects	21
Exporting projects: supported features	23
Finding media	27
Supported video formats for reading	31
Adding media and creating clips	60
Playing media	65
Previewing video	65
Navigating the timeline	72
Marking in and out points for playback	73
Track editing	75
Adding tracks to a project	75
Deleting tracks	76
Moving tracks	76

Creating a picture-in-picture effect	77
Adjusting track controls	82
Using the Track Inspector	86
Adjusting timeline settings	92
Clip editing	95
Editing tools	95
Selecting clips and positioning the cursor	98
Moving clips	99
Trimming clips	102
Stream editing (L-J cuts and rolls)	106
Splitting clips	108
Slipping clips	108
Cropping clips	111
Cutting, copying, and pasting clips	113
Deleting clips	114
Ripple edits	114
Clip snapping	115
Quantize to frames	117
Using markers	118
Nested timelines	119
Clip fades	122
Clip volume automation	123
Replacing a clip's media	127
Undoing and redoing edit operations	128
Using the Clip Inspector	128
Applying effects	135
Using video effects	135

Using video generators	141
Adding title clips	141
Adding solid-color clips	146
Adding color-gradient clips	147
Using video transitions	149
Creating a picture-in-picture effect	150
Animating video parameters with keyframes	155
Working with audio	157
Audio volume and panning	157
Working with multichannel audio	158
Monitoring audio levels	167
Track meter	168
Editing Catalyst Edit options	169
Keyboard shortcuts	171
Gestures	181
Index	183

Introduction


Catalyst Edit is your focused, fast cutting tool for 4K, RAW, and HD video.

Catalyst Edit focuses on HD, 4K, and Sony RAW video editing while you focus on creativity. Flexible timeline editing tools make working with 4K XAVC and Sony RAW files as easy as working with HD. At last, take full advantage of all the detail and high dynamic range color you shot. Catalyst Edit ends the multichannel audio nightmare with an innovative workflow that enables you to use your camera audio however you need to even without a degree in audio engineering. Catalyst Edit integrates tightly with Catalyst Prepare to provide continuity from the media prep stage to the editing stage.

The Catalyst Edit window

The Catalyst Edit window is divided into five main sections:

- The toolbars provide quick access to frequently used functions.
- The left side of the window displays the Media Browser (where you can browse your computer for media files to use in your projects) and the Plug-Ins pane (where you can browse the available video effects, generators, and transitions).
- The Video Preview displays the video frame at the cursor position and allows you to play back your project.
- The timeline is where you create projects. You can add tracks to organize your media clips and add clips to the tracks.
- The right side of the window can display the Inspector, which allows you to edit application options, properties for the timeline, selected track, or selected clip.



Notice to users

Disclaimers

Original images will change in appearance after performing image conversion with this product. Therefore, to prevent copyright infringement on copyrighted material, obtain the proper permissions from the copyright holder of the original images before conversion. IN NO EVENT SHALL SONY CORPORATION BE LIABLE FOR ANY INCIDENTAL, CONSEQUENTIAL OR SPECIAL DAMAGES, WHETHER BASED ON TORT, CONTRACT, OR OTHERWISE, ARISING OUT OF OR IN CONNECTION WITH THIS MANUAL, THE SOFTWARE OR OTHER INFORMATION CONTAINED HEREIN OR THE USE THEREOF. This software may not be used for purposes other than those specified. Sony Corporation reserves the right to make any modification to this manual or the information contained herein at any time without notice.

Software copyrights

This manual or the software described herein, in whole or in part, may not be reproduced, translated or reduced to any machine-readable form without prior written approval from Sony Creative Software Inc.

© 2023 Sony Creative Software Inc.

HEVC Advance

Covered by one or more claims of the HEVC patents listed at patentlist.accessadvance.com.



Working with projects

A project file (.ceditprj) saves the relevant information about your source media: file locations, edits, insertion points, transitions, and effects.

A project file is not a multimedia file. It contains pointers to the original source files, so you can edit your project nondestructively. You can be creative without worrying about corrupting your source files.

 Catalyst Edit saves a backup copy of your project automatically. If Catalyst Edit terminates unexpectedly, the autosaved project will be opened the next time you start.

Creating projects

The first step in creating your masterpiece is to create a Catalyst Edit project file (.ceditprj).

1. Click the Project button  in the main toolbar.
2. Choose New from the menu to create a project.

 Press Ctrl+N (Windows) or ⌘ +N (macOS) to create a new project quickly.

Opening projects

1. Click the Project button  in the main toolbar.
2. Choose Open from the menu.

 Press Ctrl+O (Windows) or ⌘ -O (macOS).

The Open dialog is displayed.

If you have not saved the current project, you are prompted to save your changes.

3. Choose the folder where the project you want to open is stored.
4. Select a Catalyst Edit project file (.ceditprj) in the browse window or type a name in the File name box.

5. Click Open.



Choose a project from the Recent Projects list to quickly open a recently edited project.

Relinking project media

When you open a project, Catalyst Edit will prompt you to relink project media if the original clips cannot be found.

You can also use the Relink Project Media dialog to create a proxy-based workflow: create a project using lower-resolution proxy clips for efficient editing and then relink the proxy clips to their full-resolution versions before rendering or exporting your project. For more information, see ["Rendering projects" on page 20](#) or ["Working with projects" on page 21](#).

1. Open a project. For more information, see ["Opening projects" on page 11](#).

If the clips used in your project are not found in their original locations, the Relink Project Media dialog is displayed.

If you want to relink media manually, click the Project button  in the main toolbar and choose Relink from the menu.

2. For each clip, the Relink Project Media dialog displays the original clip and its linked clip.

Click a folder path and browse to a new location to choose a new location for your source clips.

Click Locate Folder or Locate File (if a clip is missing) or a clip's path and browse to a new file to choose a replacement file.

 Click the  button to display the full path.

3. Click Relink. The clips are replaced, and your project is updated.

Saving projects

You can use the Save or Save As commands to save changes to the current Catalyst Edit project.

 If your project contains unsaved changes, (edited) is displayed after the project name in the title bar.

1. Click the Project button  in the main toolbar.
2. Choose Save to save the current project, or choose Save as if you are saving a new project for the first time or want to create a copy of the current project.

 Press Ctrl+S (Windows) or ⌘ -S (macOS).

The Save window is displayed.

3. Select the drive and folder where you want to store the project.
4. Type a name for the project in the File name (Windows) or Save As (macOS) box.
5. Click the Save button.

Using the Timeline Inspector

In the Inspector , select the Timeline tab to edit settings for your project timeline.

 Click an empty area in the timeline below the last track, and the Timeline tab is displayed automatically if the Inspector is visible.

When you add the first video clip to a project, the timeline settings are automatically adjusted to match the media properties. For more information, see ["Adding media and creating clips" on page 60](#).

Summary

Type a value in the Name box to set the title of the project.

Video

Item	Description
Width	Determines the frame size of your final movie when rendered.
Height	
Pixel aspect ratio	Type a value in the box to change the pixel aspect ratio of your project. Computers display pixels as squares, or a ratio of 1.0. Televisions display pixels as rectangles (ratios other than 1.0). Using the incorrect setting can result in distortion or stretching. Consult your capture/video output card's manual for the proper settings.
Frame rate	Type a value in the box to change the frame rate of your project. The ruler in the timeline is displayed using this frame rate. The television frame rate in the US, North and Central America, parts of South America, and Japan (NTSC) is 29.97 frames per second (fps). In many parts of the world, including Europe and much of Asia, the television standard is PAL at 25 fps. France, Russia, and most of Eastern Europe use SECAM, which is a variation on PAL and also uses 25 fps.

Item	Description
Working color space	<p>Choose a setting from the Working color space drop-down list to choose the color space that will be used to display your project. Choosing the correct color space ensures that you see your video in the proper color space as you work.</p> <p>If you're using media from a Catalyst Prepare library () , ensure you're using the same Working color space setting in the Catalyst Prepare Options menu and the Catalyst Edit Timeline Inspector.</p>

Audio

Item	Description
Sample rate	<p>Choose a sample rate from the drop-down list to indicate the number of samples per second used to store audio. Your project audio is resampled automatically.</p> <p>To use a custom sample rate, choose Custom from the drop-down list and type a sample rate in the edit box.</p>
Channel setup	Choose Stereo from the drop-down list to create a two-channel (stereo) project.
Channel count	Choose Multichannel and type a number in the Channel count box to create a multichannel project.
Gain	<p>Drag the fader to adjust the volume of the main output. Double-click the center of the thumb to reset the fader. You can double-click the numeric value to type a new value.</p> <p> When adjusting volume, remember to watch your audio meters. Because you are adding the volumes of all of the tracks together, it is easy to clip the audio output. Make sure that the meters never display the red Clip indication during playback. For more information, see "Monitoring audio levels" on page 167.</p>
Mute	Click  to mute/unmute your project's audio output.

Channel Output

Click the speaker icon to turn a channel on  or off .

Click the Mono or Stereo button to indicate whether a channel is a mono channel or part of a stereo pair. Enabling Stereo will pair the channel with the next channel in the list.

 If you want to set all of a clip's channels at once, click the Channel Tools button  and choose Set all to mono, Set all to stereo, or Reset.

Type a name in the edit box to identify the channel. For example, you might type Lav1 to identify audio from a lavalier microphone.

 Channels that are named identically in the Timeline Inspector and Clip Inspector will be matched.

When you add a clip from a Catalyst Prepare library () to the Catalyst Edit timeline, any channel assignment settings that you made in the Catalyst Prepare library will be applied to the clip.

Video Effects

When the timeline has effects applied to it, you can use the Video Effects controls to control the settings for each effect. For more information, see ["Adding effects to the timeline" on page 139](#).

Click the Overlay button  to show or hide a plug-in's interactive overlay controls in the video preview (when available).

Click the Mute button  to bypass a plug-in without removing it from the chain.

Click the Delete button  to remove a plug-in from the chain.

Drag a plug-in's heading to change its position in the plug-in chain.

Click the toggle arrow to show or hide each plug-in's controls.

When you select a position parameter in the Inspector, a control point () is displayed in the video preview. You can adjust the parameter's position by dragging the control point in the video preview or the Inspector:



Sharing projects

Catalyst Edit allows you to convert and upload your projects to the Web to share them.

Uploading files to YouTube

1. Click the Project button  in the main toolbar.
2. Choose Share from the menu. The Share dialog is displayed.
3. From the Upload clip to drop-down list, choose YouTube.
4. Use the Share dialog to log on to your Google account and follow the on-screen instructions to upload the selected file.
 - a. In the Title box, type a new title to identify your video.
 - b. Type a description of your movie in the Description box.
 - c. Type keywords you want to associate with your movie in the Tags box. Use words that relate to your movie and describe its content. These tags will be used when searching YouTube. Use commas to separate multiple keywords.
 - d. From the Privacy drop-down list, choose a setting to set broadcast options for your movie. Public videos can be seen by any YouTube user; private videos can be seen only by members you specify; unlisted videos can be seen by anyone who has a link to the video, but they are not included in YouTube searches.
 - e. Choose a setting from the Category drop-down list. The category you choose is used to classify videos on the YouTube site.
 - f. Choose a setting from the Resolution drop-down list to choose the frame size of the video.
 - g. Choose a setting from the Encode mode drop-down list to choose whether you want to optimize image quality or transcoding speed.
5. Select the Render loop region only check box if you want to save only the portion of the project that is contained within the Mark In/Mark Out region. For more information, see ["Marking in and out points for playback" on page 73](#).
 Loop Playback  does not need to be selected for this option to work.
6. Click Upload.

Progress is displayed in the activity pane at the top of the Catalyst Edit window. If you have multiple upload jobs queued, a separate progress indicator is displayed for each job.

Rendering projects

When you're finished editing your project – or when you want to see it in its final form – rendering converts your project to another format and creates a single file on your hard drive.

When you render your project, the project file is not affected (overwritten, deleted, or altered) during the rendering process. You may return to the original project to make edits or adjustments and render it again.

1. Click the Project button  in the main toolbar.
2. Choose Render from the menu. The Render Project dialog is displayed.
3. Type a name in the Name box to identify your rendered file.
4. In the Destination folder box, type the path to the folder where you want to save the rendered file, or click Browse to choose a folder.
5. Choose a setting from the Format menu to indicate whether you want to create an AVC/AAC (*.mp4), DNxHD, Apple ProRes (macOS only), SStP, XAVC Intra, XAVC Long, XAVC S, or XDCAM clip.



If you want to render an audio-only file, choose MP3 Audio, Sony W64 or WAV.

If you want to render an image sequence, choose DPX or OpenEXR.

6. Choose a setting from the Render preset drop-down list to choose the settings that will be used for the new file.
 Choose the Best match preset if you want Catalyst Edit to choose the most appropriate preset for your project timeline. For more information, see ["Using the Timeline Inspector" on page 14](#).
7. If you're rendering to a format that supports multichannel audio, use the controls in the Audio channels box to map your project's audio channels to the channels in the rendered file.

The left column represents the audio channels in the destination file. The drop-down lists in the right column represent the number of audio channels that have been configured for your project. For more information, see ["Working with multichannel audio" on page 158](#).

For each destination channel, choose an output from the drop-down list, or choose Unused to render silence in that channel.

8. Select the Render loop region only check box if you want to save only the portion of the project that is contained within the Mark In/Mark Out region. For more information, see ["Marking in and out points for playback" on page 73](#).



Loop Playback  does not need to be selected for this option to work.

9. Click OK.

Progress is displayed in the activity pane at the top of the Catalyst Edit window.

Exporting projects

Project-interchange tools add flexibility to your workflow, allowing you to exchange projects with other popular editing platforms.



For more information about supported features for exported projects, please see ["Exporting projects: supported features" on page 23](#). Design your Catalyst Edit project with these features in mind to ensure a smooth interchange.

1. Click the Project button  in the main toolbar.
2. Choose Export from the menu.
3. The Export project to box displays the path to the folder where the project will be exported. You can type a path in the box or click the Browse button to choose a folder.
4. Type a name in the File name box to set the file name that will be used for your exported project file.
5. Choose an export format from the Project format drop-down list:
 - Apple Final Cut Pro X (*.fcpxml)
 - Adobe Premiere (*.prproj)
 - Avid Media Composer (*.aaf)
 - Vegas Pro EDL (*.txt)
6. Choose transcoding options:
 - If you want to link to the original clips in the original locations, choose Do not transcode from the Media format drop-down list.
 - If you want to transcode the storyboard's media to another format when exporting, choose a setting from the Media format drop-down list.
7. Click Export.

Progress is displayed in the activity pane at the top of the Catalyst Edit window. If you have multiple export jobs queued, a separate progress indicator is displayed for each job.

An HTML report file is created in the same folder as the exported project with details about the export. Any warnings or errors will be displayed in the report.

Exporting projects: supported features

Catalyst Edit supports the following features when exporting projects.

 Design your Catalyst Edit project with these features in mind to ensure a smooth interchange.

Media Composer 6 (.aaf)

- Timeline (including frame rate)

 Catalyst Edit timelines are always exported as stereo.

- Markers
- Frame rate
- Clips

 Clips from nested timelines are exported to the main Media Composer timeline.

Crossfades between nested timelines and other events in the parent timeline are ignored.

Track volume, nested timeline track volume, and clip gain are summed and applied as clip gain in Media Composer.

- Audio channel routing (including timeline channel output and clip channel assignment)
- Clip audio fades and gain
 -  Audio clip gain and audio track gain are exported as clip gain.
- Overlapping clips
- Track gain (converted to clip gain)

Premiere Pro CS6 (.prproj)

- Timeline (including width, height, pixel aspect ratio, frame rate, and field order)

 Catalyst Edit timelines are always exported as stereo.

- Markers
- Clips (including nested timelines)
- Clip fades and gain/opacity

- Overlapping clips
- Title clips (multiline text, text angle, text color, background color, and shadow color are supported)
- Track gain, pan, mute, and solo

Final Cut Pro X (.fcpxml)

- Timeline

 Catalyst Edit timelines are always exported as stereo.

Projects with multichannel audio will play through the left channel only in Final Cut Pro.

- Markers (timeline markers are exported as clip markers, and markers beyond the last clip are omitted)
- Clips (including nested timelines)
- Clip fades and gain/opacity

 Video clip gain is exported as clip opacity.

Audio clip gain and audio track gain are exported as clip gain.

- Audio channel routing (including timeline channel output and clip channel assignment)
- Overlapping clips
- Title clips (title text, font, font size, bold, italics, alignment, color, shadow, outline, and rotation are supported)

 Please confirm font sizes in Final Cut Pro X after exporting your project.

- Track gain, pan, mute, and solo

Vegas EDL (.txt)

- Timeline

 Catalyst Edit timelines are always exported as stereo.

- Clips

 Clips from nested timelines are exported to the main Vegas timeline.

Crossfades between nested timelines and other events in the parent timeline are ignored.

Track volume, nested timeline track volume, and clip gain are summed and applied as clip gain in Vegas.

- Clip fades and gain/opacity:

-  Video clip gain is exported as clip opacity.

- Audio clip gain and audio track gain are exported as clip gain.

- Audio channel routing

- Overlapping clips

Finding media

The Media Browser pane allows you to browse the media files on drives and devices connected to your computer.


When you double-click a file in the Media Browser, it is added to the end of the selected track as a clip. If no track is selected, a new track is created. For more information, see ["Adding tracks to a project" on page 75](#) or ["Adding media and creating clips" on page 60](#).

Choosing a folder

Click the Media Browser button at the top of the Catalyst Edit window to view the Media Browser.

Use the Media Browser to browse your computer for video files.

The top of the Media Browser will display the current folder and its parent folder. You can click the link to the parent folder to navigate up one level.



 To navigate quickly, click the Tools button  at the bottom of the Media Browser and choose Go to location.

Displaying files in a list or thumbnail mode

Click the Media Browser Settings button  to display the Media Browser Settings menu, where you can choose to view media in grid or list mode.

In grid mode, the Media Browser displays thumbnail images and file names.

In list mode, the Media Browser displays a simple list of thumbnail images and file names.

Showing source clips

1. Select a file.
2. Click the Tools button  at the bottom of the Media Browser and choose Show in Finder (macOS) or Show in Explorer (Windows) to view the source clip in its containing folder.

 Select a clip on the timeline, click the Clip button  below the timeline, and choose Show in Finder (macOS) or Show in Explorer (Windows) to view the source clip in its containing folder.

Displaying media from a Catalyst Prepare library

You can also add media from Sony Catalyst Prepare libraries to your Catalyst Edit projects.

In the Media Browser, double-click a .cpreplib file (). When you open a Catalyst Prepare library, the Media Browser displays all the media contained in that library sorted in bins.

 The default location for .cpreplib files is C:\Users\\Videos\ on Windows and /Users/<username>/Movies/ on macOS.

If you want to use a storyboard from a Catalyst Prepare library, open a library as described above. A separate bin () is displayed for each storyboard. Drag a storyboard bin to the timeline to add it.

 You can also create clips by dragging clips from the Catalyst Prepare window to the Catalyst Edit timeline. For more information, see ["Adding media and creating clips" on page 60](#).

Previewing media from the Media Browser

Select a file in the Media Browser and click the Preview button  at the bottom of the Media Browser to play it.

During playback, the Preview button  changes to a Pause button . You can click the Pause button to suspend playback, or playback will stop at the end of the selected clip.

In grid mode, the video will play in the thumbnail. In list mode, a video preview is displayed above the file list.

Previewing clips in the primary display

Click the Media Browser Settings button  to display the Media Browser Settings menu, and then use the Primary display buttons to preview Media Browser files in the primary display above the timeline.

Item	Description
Off	The primary display is not used for previewing files from the Media Browser.
On	Files from the Media Browser are played in the Media Browser and in the primary display above the timeline.
2 Up	Files from the Media Browser are played in the Media Browser and in the left side of the primary display above the timeline. The right side of the primary display shows the frame at the cursor position in the timeline.

Previewing clips in the secondary window

If you're using the secondary window, you can choose to preview Media Browser files in the secondary window. For more information, see ["Editing Catalyst Edit options" on page 169](#).

Click the Media Browser Settings button  to display the Media Browser Settings menu, and then use the Secondary window buttons.

Item	Description
Off	The secondary window is not used for previewing files from the Media Browser.
On	Files from the Media Browser are played in the Media Browser and in the secondary window.


Item	Description
2 Up	Files from the Media Browser are played in the Media Browser and in the left side of the secondary window. The right side of the secondary window shows the frame at the cursor position in the timeline.

Using hover scrub

When Hover scrub is selected in the Media Browser Settings menu, you can hover your mouse over the play cursor in the thumbnail (or the video preview in list mode) to change the playback position and scrub the media. When the button is not selected, you can click and drag the cursor to scrub.


 You can scrub the selected clip in the Media Browser using the JKL keys: press and hold K while pressing J or L to emulate a shuttle knob mode. Press K+J to scrub left or K+L to scrub right.

In grid mode, the audio waveform is displayed in the video preview to help you navigate the file, and the timecode above the video preview displays the current cursor position. You can click the timecode to type a new value and reposition the cursor.



Setting mark in/out points in the Media Browser

Mark in/out points are displayed in the Media Browser and allow you to add partial clips to the timeline.



- Press I to set the mark in point to the cursor position or press O to set the mark out point.
- You can also drag the mark in/out points to change their positions.

When you add a clip to your project, only the area between the mark in/out points will be added to the timeline. For more information, see ["Adding media and creating clips" on page 60](#).

Managing SxS and Professional Disc volumes

If you need to format an SxS card, please use the [Memory Media Utility](#).

If you need to format or finalize an XDCAM Professional Disc volume, please use the [XDCAM Drive Software](#).

Supported video formats for reading

Catalyst Edit supports reading the following video formats from volumes or as independent clips:

XDCAM

SD format

Format	Frame Size	Frame Rate	Field Order	Video Codec	Bit Rate	Audio Channels
DV	720x480	59.94i	Lower	DV	25 CBR	4x16 bit
DV	720x576	50i	Lower	DV	25 CBR	4x16 bit
MPEG IMX	720x512	59.94i	Upper	MPEG-2 Intra	30, 40, 50 CBR	4x24 bit / 8x16 bit
MPEG IMX	720x608	50i	Upper	MPEG-2 Intra	30, 40, 50 CBR	4x24 bit / 8x16 bit
Uncompressed	720x486	59.94i	Upper	Uncompressed	90 CBR	4x24 bit / 8x16 bit
Uncompressed	720x576	50i	Upper	Uncompressed	90 CBR	4x24 bit / 8x16 bit

HD format

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Video Codec	Bit Rate
MPEG HD	1280x720	1.0	50p, 59.94p	MPEG-2 Long GOP	25 CBR
MPEG HD	1280x720	1.0	50p, 59.94p	MPEG-2 Long GOP	35 VBR
MPEG HD	1280x720	1.0	50p, 59.94p	MPEG-2 Long GOP	50 CBR
MPEG HD	1440x1080	1.333	23.976p, 25p, 29.97p, 50i, 59.94i	MPEG-2 Long GOP	17.5 CBR
MPEG HD	1440x1080	1.333	23.976p, 25p, 29.97p, 50i, 59.94i	MPEG-2 Long GOP	25 CBR
MPEG HD	1440x1080	1.333	23.976p, 25p, 29.97p, 50i, 59.94i	MPEG-2 Long GOP	35 CBR
MPEG HD	1440x540	0.667	23.976p, 25p, 29.97p, Over Crank	MPEG-2 Long GOP	8.75 CBR
MPEG HD	1440x540	0.667	23.976p, 25p, 29.97p, Over Crank	MPEG-2 Long GOP	12.5 CBR
MPEG HD	1440x540	0.667	23.976p, 25p, 29.97p, Over Crank	MPEG-2 Long GOP	17.5 CBR
MPEG HD422	1920x1080	1.0	23.976p, 25p, 29.97p, 50i, 59.94i	MPEG-2 Long GOP	35 CBR, 50 CBR
MPEG HD422	1920x540	0.5	23.976p, 25p, 29.97p, Over Crank	MPEG-2 Long GOP	25 CBR

XDCAM EX

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Field Order	Video Codec	Audio Codec	Bit Rate
DV	720x480	0.9091	59.94p	Lower	DV	PCM, 48 kHz,	25 CBR

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Field Order	Video Codec	Audio Codec	Bit Rate
						16 bit	
DV	720x576	1.0926	50i	Lower	DV	PCM, 48 kHz, 16 bit	25 CBR
MPEG HD (EX-HQ)	1280x720	1.0	23.976p, 25p, 29.97p, 50p, 59.94p		MPEG-2 Long GOP	PCM, 48 kHz, 16 bit	35 VBR
MPEG HD (EX-SP)	1440x1080	1.333	50i, 59.94i		MPEG-2 Long GOP	PCM, 48 kHz, 16 bit	25 CBR
MPEG HD (EX-HQ)	1440x1080	1.333	23.976p, 25p, 29.97p, 50i, 59.94i		MPEG-2 Long GOP	PCM, 48 kHz, 16 bit	35 VBR
MPEG HD422 (EX-HQ)	1920x1080	1.0	23.976p, 25p, 29.97p, 50i, 59.94i		MPEG-2 Long GOP	PCM, 48 kHz, 16 bit	35 VBR

XAVC Intra

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Video Codec	Audio Channels (PCM, 48 kHz, 24 bit)	Bit Rate
XAVC Intra	1440x1080	1.333	50i, 59.94i, 23.976p, 25p, 29.97p	MPEG-4 AVC Intra	8	CBG 50
XAVC Intra	1920x1080	1.0	50i, 59.94i, 23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Intra	8, 16	CBG 100
XAVC Intra	1920x1080	1.0	50i, 59.94i, 23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Intra	8	CBG 200
XAVC Intra HFR	1920x1080	1.0	50p, 50i, 59.94p, 59.94i	MPEG-4 AVC Intra	0	CBG 100
XAVC Intra	2048x1080	1.0	23.976p, 24p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Intra	8	VBR
XAVC Intra	2048x1080	1.0	23.976p, 24p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Intra	8, 16	CBG 100
XAVC Intra	3840x2160	1.0	23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Intra	8	VBR
XAVC Intra	3840x2160	1.0	23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Intra	8, 16	CBG 300
XAVC Intra	4096x2160	1.0	23.976p, 24p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Intra	8	VBR
XAVC Intra	4096x2160	1.0	23.976p, 24p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Intra	8, 16	CBG 300

XAVC Long-GOP

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Video Codec	Audio	Bit Rate
XAVC Long	1280x720	1.0	50p, 59.94p	MPEG-4 AVC Long, High 422 Profile	4-channel PCM, 48 kHz, 24 bit	80 (Maximum)
XAVC Long	1920x1080	1.0	23.976p, 25p, 29.97p, 50p, 50i, 59.94p, 59.94i	MPEG-4 AVC Long, High 422 Profile	4-channel PCM, 48 kHz, 24 bit	80 (Maximum)
XAVC Long	3840x2160	1.0	23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Long, High Profile	4-channel PCM, 48 kHz, 24 bit	200 (Maximum)
XAVC Long Proxy	480x270	1.0	23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Long, High Profile	MPEG-4 AAC, 2 channels, 48 kHz, 256 kbps MPEG-4 AAC, 6 (5.1) channels, 48 kHz, 640 kbps	1 or .5 Mbps
XAVC Long Proxy	640x360	1.0	23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Long, High Profile	MPEG-4 AAC, 2 channels, 48 kHz, 256 kbps	3 Mbps

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Video Codec	Audio	Bit Rate
					MPEG-4 AAC, 6 (5.1) channels, 48 kHz, 640 kbps	
XAVC Long Proxy	1280x720	1.0	23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Long, High Profile	MPEG-4 AAC, 2 channels, 48 kHz, 256 kbps	9 Mbps
					MPEG-4 AAC, 6 (5.1) channels, 48 kHz, 640 kbps	

XAVC S

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Video Codec	Audio	Bit Rate
XAVC Long Proxy	480x270	1.0	23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Long, High Profile	MPEG-4 AAC, 2 channels, 48 kHz, 256 kbps	4
XAVC Long Proxy	640x360	1.0	23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Long, High Profile	MPEG-4 AAC, 2 channels, 48 kHz, 256 kbps	10
XAVC Long	1280x720	1.0	23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Long, Main Profile or High Profile	2-channel PCM, 48 kHz, 16 bit 4-channel PCM, 48 kHz, 24 bit	40
XAVC Long Proxy	1280x720	1.0	23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Long, High Profile	MPEG-4 AAC, 2 channels, 48 kHz, 256 kbps	16
XAVC Long	1280x720	1.0	100p, 119.88p	MPEG-4 AVC Long, Main Profile or High Profile	2-channel PCM, 48 kHz, 16 bit 4-channel PCM, 48 kHz, 24 bit	80
XAVC Long	1440x1080	1.0	23.976p, 25p, 29.97p, 50p	MPEG-4 AVC Long, Main Profile or High Profile	2-channel PCM, 48 kHz, 16 bit 4-channel	80

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Video Codec	Audio	Bit Rate
			59.94p		PCM, 48 kHz, 24 bit	
XAVC Long	1920x1080	1.0	23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Long, Main Profile or High Profile	2-channel PCM, 48 kHz, 16 bit 2/4-channel PCM, 48 kHz, 24 bit	80
XAVC Long	1920x1080	1.0	100p, 119.88p	MPEG-4 AVC Long, Main Profile or High Profile	2-channel PCM, 48 kHz, 16 bit 2/4-channel PCM, 48 kHz, 24 bit	150
XAVC Long Proxy	1920x1080	1.0	23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Long, High Profile	MPEG-4 AAC, 2 channels, 48 kHz, 256 kbps	25
XAVC Long	1920x1080	1.0	25p, 30p	AVC S Long 4:2:0 8-bit MP4	MPEG-4 AAC, 2 channels, 48 kHz, 256 kbps	16 50
XAVC Long	1920x1080	1.0	50p, 60p	AVC S Long 4:2:0 8-bit MP4	MPEG-4 AAC, 2 channels, 48 kHz, 256 kbps	25 50
XAVC Long	1920x1080	1.0	24p	AVC S Long 4:2:0 8 bit-MP4	MPEG-4 AAC, 2 channels,	50

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Video Codec	Audio	Bit Rate
					48 kHz, 256 kbps	
XAVC Long	1920x1080	1.0	100p, 120p	AVC S Long 4:2:0 8 bit-MP4	MPEG-4 AAC, 2 channels, 48 kHz, 256 kbps	60 100
XAVC Long	1920x1080	1.0	24p, 25p, 30p,50p, 60p	XAVC S Long 4:2:2 10-bit MP4	2-channel PCM, 48 kHz, 16 bit 2/4- channel PCM, 48 kHz, 24 bit	50
XAVC Intra	1920x1080	1.0	24p	XAVC S Intra 4:2:2 10-bit MP4	2-channel PCM, 48 kHz, 16 bit 2/4- channel PCM, 48 kHz, 24 bit	89
XAVC Intra	1920x1080	1.0	25p	XAVC S Intra 4:2:2 10-bit MP4	2-channel PCM, 48 kHz, 16 bit 2/4- channel PCM, 48 kHz, 24 bit	93
XAVC Intra	1920x1080	1.0	30p	XAVC S Intra 4:2:2 10-bit MP4	2-channel PCM, 48 kHz, 16 bit 2/4- channel	111

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Video Codec	Audio	Bit Rate
					PCM, 48 kHz, 24 bit	
XAVC Intra	1920x1080	1.0	50p	XAVC S Intra 4:2:2 10-bit MP4	2-channel PCM, 48 kHz, 16 bit 2/4-channel PCM, 48 kHz, 24 bit	185
XAVC Intra	1920x1080	1.0	60p	XAVC S Intra 4:2:2 10-bit MP4	2-channel PCM, 48 kHz, 16 bit 2/4-channel PCM, 48 kHz, 24 bit	222
XAVC Long	3840x2160	1.0	23.976p, 25p, 29.97p	MPEG-4 AVC Long, Main Profile or High Profile	2-channel PCM, 48 kHz, 16 bit 2/4-channel PCM, 48 kHz, 24 bit	188
XAVC Long	3840x2160	1.0	50p, 59.94p	MPEG-4 AVC Long, Main Profile or High Profile	2-channel PCM, 48 kHz, 16 bit 2/4-channel PCM, 48 kHz, 24 bit	200
XAVC Long	3840x2160	1.0	100p, 119.88p	MPEG-4 AVC Long, Main Profile or High Profile	2-channel PCM, 48 kHz, 16 bit	200

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Video Codec	Audio	Bit Rate
				Profile	2/4-channel PCM, 48 kHz, 24 bit	
XAVC Long	3840x2160	1.0	24p, 25p, 30p	XAVC S Long 4:2:0 8-bit MP4	2-channel PCM, 48 kHz, 16 bit	60 100
					2/4-channel PCM, 48 kHz, 24 bit	
XAVC Long	3840x2160	1.0	50p, 60p	XAVC S Long 4:2:0 8-bit MP4	2-channel PCM, 48 kHz, 16 bit	150
					2/4-channel PCM, 48 kHz, 24 bit	
XAVC Long	3840x2160	1.0	100p, 120p	XAVC S Long 4:2:0 8-bit MP4	2-channel PCM, 48 kHz, 16 bit	200
					2/4-channel PCM, 48 kHz, 24 bit	
XAVC Long	3840x2160	1.0	24p	XAVC S Long 4:2:2 10-bit MP4	2-channel PCM, 48 kHz, 16 bit	100
					2/4-channel PCM, 48 kHz, 24 bit	
XAVC Long	3840x2160	1.0	25p, 30p	XAVC S Long	2-channel	140

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Video Codec	Audio	Bit Rate
				4:2:2 10-bit MP4	PCM, 48 kHz, 16 bit 2/4- channel PCM, 48 kHz, 24 bit	
XAVC Long	3840x2160	1.0	50p, 60p	XAVC S Long 4:2:2 10-bit MP4	2-channel PCM, 48 kHz, 16 bit 2/4- channel PCM, 48 kHz, 24 bit	200
XAVC Long	3840x2160	1.0	100p, 120p	XAVC S Long 4:2:2 10-bit MP4	2-channel PCM, 48 kHz, 16 bit 2/4- channel PCM, 48 kHz, 24 bit	280
XAVC Long	3840x2160	1.0	24p	XAVC S Long 4:2:2 10-bit MP4	2-channel PCM, 48 kHz, 16 bit 2/4- channel PCM, 48 kHz, 24 bit	100
XAVC Intra	3840x2160	1.0	24p	XAVC S Intra 4:2:2 10-bit MP4	2-channel PCM, 48 kHz, 16 bit 2/4- channel PCM, 48	240

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Video Codec	Audio	Bit Rate
					kHz, 24 bit	
XAVC Intra	3840x2160	1.0	25p	XAVC S Intra 4:2:2 10-bit MP4	2-channel PCM, 48 kHz, 16 bit 2/4- channel PCM, 48 kHz, 24 bit	250
XAVC Intra	3840x2160	1.0	30p	XAVC S Intra 4:2:2 10-bit MP4	2-channel PCM, 48 kHz, 16 bit 2/4- channel PCM, 48 kHz, 24 bit	300
XAVC Intra	3840x2160	1.0	50p	XAVC S Intra 4:2:2 10-bit MP4	2-channel PCM, 48 kHz, 16 bit 2/4- channel PCM, 48 kHz, 24 bit	500
XAVC Intra	3840x2160	1.0	60p	XAVC S Intra 4:2:2 10-bit MP4	2-channel PCM, 48 kHz, 16 bit 2/4- channel PCM, 48 kHz, 24 bit	600
XAVC Intra	4096x2160	1.0	24p	XAVC S Intra 4:2:2 10-bit MP4	2-channel PCM, 48 kHz, 16 bit	230

XAVC HS

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Video Codec	Audio	Bit Rate
HEVC Proxy	1920x1080	1.0	23.976p, 30p, 50p, 59.94, 100p, 119,98p	HEVC Long, 10-bit, 4:2:0	2-channel PCM, 48 kHz, 16 bit or 24 bit	16
HEVC	3840x2160	1.0	23.976p	HEVC Long, 10-bit, 4:2:0	2/4-channel PCM, 48 kHz, 16 bit or 24 bit	30
HEVC	3840x2160	1.0	50p	HEVC Long, 10-bit, 4:2:0	2/4-channel PCM, 48 kHz, 16 bit or 24 bit	45
HEVC	3840x2160	1.0	59.94p	HEVC Long, 10-bit, 4:2:0	2/4-channel PCM, 48 kHz, 16 bit or 24 bit	78
HEVC	3840x2160	1.0	100p	HEVC Long, 10-bit, 4:2:0	2/4-channel PCM, 48 kHz, 16 bit or 24 bit	200
HEVC	3840x2160	1.0	119.88p	HEVC Long, 10-bit, 4:2:0	2/4-channel PCM, 48 kHz, 16 bit or 24 bit	200
HEVC	3840x2160	1.0	23.976p	HEVC Long, 10-bit, 4:2:2	2/4-channel PCM, 48 kHz, 16 bit or 24 bit	60
HEVC	3840x2160	1.0	50p	HEVC Long, 10-bit, 4:2:2	2/4-channel PCM, 48 kHz, 16 bit or 24 bit	200
HEVC	3840x2160	1.0	59.94p	HEVC Long, 10-bit, 4:2:2	2/4-channel PCM, 48 kHz, 16 bit or 24 bit	100
HEVC	3840x2160	1.0	100p	HEVC Long, 10-bit, 4:2:2	2/4-channel PCM, 48 kHz, 16 bit or 24 bit	280
HEVC	3840x2160	1.0	119.88p	HEVC	2/4-channel	280

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Video Codec	Audio	Bit Rate
				Long, 10-bit, 4:2:2	PCM, 48 kHz, 16 bit or 24 bit	
HEVC	3840x2160	1.0	24p	XAVC	2-channel	30
				HS Long	PCM, 48 kHz, 16 bit	50
				4:2:0 10-bit MP4	2/4-channel	100
					PCM, 48 kHz, 24 bit	
HEVC	3840x2160	1.0	50p, 60p	XAVC	2-channel	45
				HS Long	PCM, 48 kHz, 16 bit	75
				4:2:0 10-bit MP4	2/4-channel	150
					PCM, 48 kHz, 24 bit	
HEVC	3840x2160	1.0	100p, 120p	XAVC	2-channel	200
				HS Long	PCM, 48 kHz, 16 bit	
				4:2:0 10-bit MP4	2/4-channel	
					PCM, 48 kHz, 24 bit	
HEVC	3840x2160	1.0	24p	XAVC	2-channel	50
				HS Long	PCM, 48 kHz, 16 bit	100
				4:2:2 10-bit MP4	2/4-channel	
					PCM, 48 kHz, 24 bit	
HEVC	3840x2160	1.0	50p, 60p	XAVC	2-channel	100
				HS Long	PCM, 48 kHz, 16 bit	200
				4:2:2 10-bit MP4	2/4-channel	
					PCM, 48 kHz, 24 bit	

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Video Codec	Audio	Bit Rate
HEVC	3840x2160	1.0	100p, 120p	XAVC HS Long 4:2:2 10-bit MP4	2-channel PCM, 48 kHz, 16 bit 2/4-channel PCM, 48 kHz, 24 bit	280
HEVC	7680x4320	1.0	23.976p, 25p, 29.97p	HEVC Long, 10- bit, 4:2:0	2/4-channel PCM, 48 kHz, 16 bit or 24 bit	204
HEVC	7680x4320	1.0	23.976p, 25p, 29.97p	HEVC Long, 10- bit, 4:2:2	2/4-channel PCM, 48 kHz, 16 bit or 24 bit	260, 520

XAVC H

Format	Frame Size	Bits	Frame Rate	Quality
HEVC Long	7680x4320	10	23.976p, 25p, 29.97p	520 Mbs
HEVC Intra	7680x4320	10	23.976p, 25p, 29.97p	SQ, HQ
HEVC Intra	8192x4320	10	23.976p, 24p, 25p, 29.97p	SQ, HQ

XAVC Proxy

Format	Frame Size	Frame Rate	Video Codec	Audio	Bit Rate
XAVC Proxy	480x270	23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Long, Main Profile	MPEG-4 AAC, 2 channels, 48 kHz, 256 kbps	4
XAVC Proxy	640x360	23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Long, Main Profile	MPEG-4 AAC, 2 channels, 48 kHz, 256 kbps	10
XAVC Proxy	720x480	59.94i	MPEG-4 AVC Long, Main Profile	MPEG-4 AAC, 2 channels, 48 kHz, 256 kbps	10
XAVC Proxy	720x576	50i	MPEG-4 AVC Long, Main Profile	MPEG-4 AAC, 2 channels, 48 kHz, 256 kbps	10
XAVC Proxy	1280x720	23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Long, Main Profile or High Profile	MPEG-4 AAC, 2 channels, 48 kHz, 256 kbps	28
XAVC Proxy	1920x1080	50i, 59.94i, 23.976p, 25p, 29.97p, 50p, 59.94p	MPEG-4 AVC Long, Main Profile or High Profile	MPEG-4 AAC, 2 channels, 48 kHz, 256 kbps	28

X-OCN

Format	Frame Size	Bits	Frame Rate	Quality
X-OCN	2048x1080	16	23.976p, 24p, 25p, 29.97p, 50p, 59.94p, HFR (max. 240)	LT, ST, XT
X-OCN	3840x2160	16	23.976p, 24p, 25p, 29.97p, 50p, 59.94p, HFR (max. 120p)	LT, ST, XT
X-OCN	4096x1716	16	23.976p, 24p, 25p, 29.97p	LT, ST, XT
X-OCN	4096x2160	16	23.976p, 24p, 25p, 29.97p, 50p, 59.94p, HFR (max. 120p)	LT, ST, XT

Format	Frame Size	Bits	Frame Rate	Quality
X-OCN	4096x3024	16	23.976p, 24p, 25p, 29.97p,	LT, ST, XT
X-OCN	4096x3432	16	23.976p, 24p, 25p, 29.97p	LT, ST, XT
X-OCN	6048x2534	16	23.976p, 24p, 25p, 29.97p	LT, ST, XT
X-OCN	6054x3192	16	23.976p, 24p, 25p, 29.97p	LT, ST, XT
X-OCN	5674x3192	16	23.976p, 24p, 25p, 29.97p	LT, ST, XT
X-OCN	5760x3036	16	23.976p, 24p, 25p, 29.97p, 50p, 59.94p	LT
X-OCN	5760x3240	16	23.976p, 25p, 29.97p, 50p, 59.94p	LT
X-OCN	6052x3192	16	23.976p, 24p, 25p, 29.97p, 50p, 59.94p	LT
X-OCN	6052x3404	16	23.976p, 25p, 29.97p, 50p, 59.94p	LT
X-OCN	6054x3272	16	23.976p, 24p, 25p, 29.97p	LT, ST, XT
X-OCN	6048x4032	16	23.976p, 24p, 25p	LT, ST, XT
X-OCN	8632x4552	16	23.976p, 24p, 25p, 29.97p	LT
X-OCN	8632x4856	16	23.976p, 25p, 29.97p	LT

RAW

Format	Frame Size	Bits	Frame Rate	Compression
F5/F55RAW	2048x1080	16	23.976p, 24p, 25p, 29.97p, 50p, 59.94p, HFR (max. 240)	SQ
F5/F55RAW	3840x2160	16	23.976p, 24p, 25p, 29.97p, 50p, 59.94p, HFR (max. 120p)	SQ
F5/F55RAW	4096x2160	16	23.976p, 24p, 25p, 29.97p, 50p, 59.94p, HFR (max. 120p)	SQ
F65RAW	4096x2160	16	23.976p, 24p, 25p, 29.97p, 50p, 59.94p, HFR (max. 120)	Lite, SQ
FS700RAW	2048x1080	16	23.976p, 25p, 29.97p, 50p, 59.94p,	SQ

Format	Frame Size	Bits	Frame Rate	Compression
HFR (max. 240)				
FS700RAW	4096x2160	16	23.976p, 25p, 29.97p, 50p, 59.94p, HFR (max. 120)	SQ

HDCAM SR (SStP)

Format	Frame Size	Bits	Color Space	Pixel Aspect Ratio	Frame Rate	Compression (Mbps)
SSTP	1280x720	10	YUV 422	1.0	50p, 59.94p	Lite(220), SQ (440)
SSTP	1920x1080	10	YUV 422	1.0	50i, 59.94i, 23.976p, 24p, 25p, 29.97p, 50p, 59.94p	Lite(220), SQ (440)
SSTP	1920x1080	10	RGB 444	1.0	50i, 59.94i, 23.976p, 24p, 25p, 29.97p, 50p, 59.94p	SQ(440), HQ (880)
SSTP	1920x1080	12	RGB 444	1.0	50i, 59.94i, 23.976p, 24p, 25p, 29.97p, 50p, 59.94p	HQ(880)
SSTP	2048x1080	10	YUV 422	1.0	50p, 59.94p	Lite(220), SQ (440)
SSTP	2048x1080	10	RGB 444	1.0	50i, 59.94i, 23.976p, 24p, 25p, 29.97p	SQ(440)
SSTP	2048x1080	10	RGB 444	1.0	23.976p, 24p, 25p, 29.97p	HQ(880)
SSTP	2048x1080	12	RGB 444	1.0	50i, 59.94i, 23.976p, 24p, 25p, 29.97p	SQ(440)
SSTP	2048x1080	12	RGB 444	1.0	23.976p, 24p, 25p, 29.97p, 50p,	HQ(880)

Format	Frame Size	Bits	Color Space	Pixel Aspect Ratio	Frame Rate	Compression (Mbps)
					59.94p	
SSTP	2048x1080	12	RGB 444	1.0	23.976p, 24p, 25p, 29.97p	SQ(440)
SSTP	2048x1080	12	RGB 444	1.0	23.976p, 24p, 25p, 29.97p, 50p, 59.94p	HQ(880)
SSTP	2048x1556	10	RGB 444	1.0	23.976p, 24p, 25p	HQ(880)

NXCAM

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Video Codec	Audio Codec	Bit Rate
AVCHD	1920x1080	1.0	59.94p, 50p,	H.264/MPEG-4 AVC	Dolby AC-3 or PCM 2 channels, 48 kHz, 16 bit	28 Mbps
AVCHD	1920x1080	1.0	59.94i, 50i, 29.97p, 25p, 23.976p	H.264/MPEG-4 AVC	Dolby AC-3 or PCM 2 channels, 48 kHz, 16 bit	24 or 17 Mbps
AVCHD	1280x720	1.0	59.94p, 50p	H.264/MPEG-4 AVC	Dolby AC-3 or PCM 2 channels, 48 kHz, 16 bit	24 or 17 Mbps
AVCHD	1440x1080	1.333	59.94i, 50i	H.264/MPEG-4 AVC	Dolby AC-3 or PCM 2 channels, 48 kHz, 16 bit	9 or 5 Mbps
MPEG-2 SD	720x480	0.9091 or 1.2121	23.976p, 29.97p, 59.94i	MPEG-2	Dolby AC-3 2 channels, 48 kHz, 16 bit	9 Mbps
MPEG-2 SD	720x576	1.0926 or 1.4568	25p, 50i	MPEG-2	Dolby AC-3 2 channels, 48 kHz, 16 bit	9 Mbps

AVC H.264/MPEG-4

Format	Frame Size	Screen Aspect Ratio	Frame Rate	Video Codec	Audio Codec	Bit Rate
H.264/MPEG-4 AVC	1280x720	16:9	50p, 100p, 120p,	AVC, 8-bit, 4:2:0	Mono, 48kHz, AAC compression w/ AGC	
H.264/MPEG-4 AVC	1920x1080	16:9	24p, 25p, 30p, 48p, 50p, 60p	AVC, 8-bit, 4:2:0	Mono, 48kHz, AAC compression w/ AGC	
H.264/MPEG-4 AVC	1920x1440	4:3	24p, 25p, 30p, 48p	AVC, 8-bit, 4:2:0	Mono, 48kHz, AAC compression w/ AGC	
H.264/MPEG-4 AVC	3840x2160	16:9	23.97p, 24p, 25p, 29.97p, 50p, 59.94p	AVC, 8-bit, 4:2:0	Mono, 48kHz, AAC compression w/ AGC	
H.264/MPEG-4 AVC	4096x2160	17:9	12p	AVC, 8-bit, 4:2:0	Mono, 48kHz, AAC compression w/ AGC	
H.264/MPEG-4 AVC	2704x1524	16:9	25p, 30p	AVC, 8-bit, 4:2:0	Mono, 48kHz, AAC compression w/ AGC	
H.264/MPEG-4 AVC	2704x1440	17:9	24p	AVC, 8-bit, 4:2:0	Mono, 48kHz, AAC compression w/ AGC	
H.264/MPEG-4 AVC	1280x960	4:3	48p, 100p	AVC, 8-bit, 4:2:0	Mono, 48kHz, AAC compression w/ AGC	

Format	Frame Size	Screen Aspect Ratio	Frame Rate	Video Codec	Audio Codec	Bit Rate
H.264/MPEG-4 AVC	848x480	16:9	240p	AVC, 8-bit, 4:2:0	Mono, 48kHz, AAC compression w/ AGC	
H.264/MPEG-4 AVC	640x480	4:3	25p, 30p	AVC, 8-bit, 4:2:0	Mono, 48kHz, AAC compression w/ AGC	
H.264/MPEG-4 AVC	240x180		25p, 29.97p	AVC, 8-bit, 4:2:0	2 channels, 16 bit, AAC compression w/ AGC	
H.264/MPEG-4 AVC	320x180		25p, 29.97p	AVC, 8-bit, 4:2:0	2 channels, 16 bit, AAC compression w/ AGC	
H.264/MPEG-4 AVC	320x240		25p, 29.97p	AVC, 8-bit, 4:2:0	2 channels, 16 bit, AAC compression w/ AGC	
H.264/MPEG-4 AVC	480x270		25p, 29.97p	AVC, 8-bit, 4:2:0	2 channels, 16 bit, AAC compression w/ AGC	
H.264/MPEG-4 AVC	640x480		25p, 29.97p	AVC, 8-bit, 4:2:0	2 channels, 16 bit, AAC compression w/ AGC	
H.264/MPEG-4 AVC	1280x720		50p, 60p, 100p, 120p	AVC, 8-bit, 4:2:0	2 channels, 16 bit, AAC compression w/ AGC	
H.264/MPEG-4 AVC	1280x960		48p, 100p, 120p	AVC, 8-bit,	2 channels, 16 bit, AAC	

Format	Frame Size	Screen Aspect Ratio	Frame Rate	Video Codec	Audio Codec	Bit Rate
				4:2:0	compression w/ AGC	
H.264/MPEG-4 AVC	1920x1080		24p, 25p, 29.97p, 48p, 50p, 60p	AVC, 8-bit, 4:2:0	2 channels, 16 bit, AAC compression w/ AGC	
H.264/MPEG-4 AVC	1920x1440		24p, 25p, 29.97p, 48p	AVC, 8-bit, 4:2:0	2 channels, 16 bit, AAC compression w/ AGC	
H.264/MPEG-4 AVC	2704x1524		24p, 25p, 29.97p	AVC, 8-bit, 4:2:0	2 channels, 16 bit, AAC compression w/ AGC	
H.264/MPEG-4 AVC	3840x2160		23.97p, 24p, 25p, 29.97p, 50p, 59.94p	AVC, 8-bit, 4:2:0	2 channels, 16 bit, AAC compression w/ AGC	
H.264/MPEG-4 AVC	4096x2160		12p	AVC, 8-bit, 4:2:0	2 channels, 16 bit, AAC compression w/ AGC	
H.264/MPEG-4 AVC (HVO)	720x480		59.94i	AVC, 8-bit, 4:2:0	2 channels, 16 bit, AAC compression w/ AGC	
H.264/MPEG-4 AVC (HVO)	720x576		50i	AVC, 8-bit, 4:2:0	2 channels, 16 bit, AAC compression w/ AGC	

AS-11 DPP MXF

Format	Frame Size	Frame Rate	Video Codec	Audio Codec	Bit Rate
IMX-50	720x576	25	MPEG-2 Intra	PCM, 48 kHz, 24 bit	
XAVC Intra	1920x1080	25	MPEG-4 AVC Intra	PCM, 48 kHz, 24 bit	

Avid DNxHD®

Container: MOV or MXF

Audio Codec: PCM 44.1 kHz or 48 kHz, 16 bit or 24 bit

Frame Size	Family Name	Color Space/Bits	Frame Rate/Maximum Bit Rate
1920x1080	Avid DNxHD® 444	4:4:4 10 bit	29.97p @ 440 Mbps, 25p @ 365 Mbps, 24p @ 350 Mbps, 23.976p @ 350 Mbps
1920x1080	Avid DNxHD® 220x	4:2:2 10 bit	60p @ 440 Mbps, 59.94p @ 440 Mbps, 50p @ 365 Mbps, 59.94i @ 220 Mbps, 50i @ 185 Mbps, 29.97p @ 220 Mbps, 25p @ 185 Mbps, 24p @ 175 Mbps, 23.976p @ 175 Mbps
1920x1080	Avid DNxHD® 220	4:2:2 8 bit	60p @ 440 Mbps, 59.94p @ 440 Mbps, 50p @ 365 Mbps, 59.94i @ 220 Mbps, 50i @ 185 Mbps, 29.97p @ 220 Mbps, 25p @ 185 Mbps, 24p @ 175 Mbps, 23.976p @ 175 Mbps
1920x1080	Avid DNxHD® 145	4:2:2 8 bit	60p @ 290 Mbps, 59.94p @ 290 Mbps, 50p @ 240 Mbps, 59.94i @ 145 Mbps, 50i @ 120 Mbps, 29.97p @ 145 Mbps, 25p @ 120 Mbps, 24p @ 115 Mbps, 23.976p @ 115 Mbps
1920x1080	Avid DNxHD® 145 (subsampled to 1440x1080)	4:2:2 8 bit	59.94i @ 145 Mbps, 50i @ 120 Mbps
1920x1080	Avid DNxHD® 100 (subsampled to 1440x1080)	4:2:2 8 bit	59.94i @ 100 Mbps, 50i @ 85 Mbps, 29.97p @ 100 Mbps, 25p @ 85 Mbps, 24p @ 80 Mbps, 23.976p @ 80 Mbps
1920x1080	Avid DNxHD® 36	4:2:2 8 bit	60p @ 90 Mbps, 59.94p @ 90 Mbps, 50p @ 75 Mbps, 29.97p @ 45 Mbps, 25p @ 36 Mbps, 24p @ 36 Mbps, 23.976p @ 36 Mbps
1280x720	Avid DNxHD® 220x	4:2:2 10 bit	59.94p @ 220 Mbps, 50p @ 175 Mbps, 29.97p @ 110 Mbps, 25p @ 90 Mbps, 23.976p @ 90 Mbps
1280x720	Avid DNxHD®	4:2:2 8 bit	59.94p @ 220 Mbps, 50p @ 175 Mbps,

Frame Size	Family Name	Color Space/Bits	Frame Rate/Maximum Bit Rate
	220		29.97p @ 110 Mbps, 25p @ 90 Mbps, 23.976p @ 90 Mbps
1280x720	Avid DNxHD® 145	4:2:2 8 bit	59.94p @ 145 Mbps, 50p @ 115 Mbps, 29.97p @ 75 Mbps, 25p @ 60 Mbps, 23.976p @ 60 Mbps
1280x720	Avid DNxHD® 100 (subsampled to 960x720)	4:2:2 8 bit	59.94p @ 100 Mbps, 50p @ 85 Mbps, 29.97p @ 50 Mbps, 25p @ 45 Mbps, 23.976p @ 50 Mbps

Apple ProRes

Container: MOV

Audio Codec: PCM

Format	Frame Size	Frame Rate	Video Codec
ProRes	720x486	59.94i, 30p, 29.97p, 24p, 23.976p	422 (proxy), 422 (LT), 422, 422 (HQ), 4444, 4444 XQ (Windows only)
ProRes	720x576	50i, 25p	422 (proxy), 422 (LT), 422, 422 (HQ), 4444, 4444 XQ (Windows only)
ProRes	960x720	60p, 59.94p, 50p, 30p, 29.97p, 24p, 23.976p	422 (proxy), 422 (LT), 422, 422 (HQ), 4444, 4444 XQ (Windows only)
ProRes	1280x720	60p, 59.94p, 50p, 30p, 29.97p, 24p, 23.976p	422 (proxy), 422 (LT), 422, 422 (HQ), 4444, 4444 XQ (Windows only)
ProRes	1280x1080	59.94i, 30p, 29.97p, 24p, 23.976p	422 (proxy), 422 (LT), 422, 422 (HQ), 4444, 4444 XQ (Windows only)
ProRes	1440x1080	59.94i, 50i, 30p, 29.97p, 25p, 24p, 23.976p	422 (proxy), 422 (LT), 422, 422 (HQ), 4444, 4444 XQ (Windows only)
ProRes	1920x1080	60p, 59.94p, 50p, 59.94i, 50i, 30p, 29.97p, 25p, 24p, 23.976p	422 (proxy), 422 (LT), 422, 422 (HQ), 4444, 4444 XQ (Windows only)
ProRes	2048x1080	60p, 59.94p, 50p, 30p, 29.97p, 25p, 24p, 23.976p	422 (proxy), 422 (LT), 422, 422 (HQ), 4444, 4444 XQ (Windows only)
ProRes	2048x1556	60p, 59.94p, 50p, 30p, 29.97p, 25p, 24p, 23.976p	422 (proxy), 422 (LT), 422, 422 (HQ), 4444, 4444 XQ (Windows only)
ProRes	3840x2160	60p, 59.94p, 50p, 30p, 29.97p, 25p, 24p, 23.976p	422 (proxy), 422 (LT), 422, 422 (HQ), 4444, 4444 XQ (Windows only)

Format	Frame Size	Frame Rate	Video Codec
ProRes	4096x2160	60p, 59.94p, 50p, 30p, 29.97p, 25p, 24p, 23.976p	422 (proxy), 422 (LT), 422, 422 (HQ), 4444, 4444 XQ (Windows only)
ProRes	5120x2160	60p, 59.94p, 50p, 30p, 29.97p, 25p, 24p, 23.976p	422 (proxy), 422 (LT), 422, 422 (HQ), 4444 , 4444 XQ (Windows only)

HDV

Container: MPEG-2 Transport Stream (Windows), MOV (macOS)

Audio Codec: MPEG-1 Audio Layer-2 (Windows). 2 channels, 48 kHz, 16 bit

Format	Frame Size	Pixel Aspect Ratio	Frame Rate	Interlace	Video Codec
HDV	1440x1080	1.333	50i, 59.94i	Upper	MPEG-2 MP@H14

DV

Container: AVI (Windows), MOV (macOS)

Audio Codec: PCM, 2 channels, 32 kHz, 16 bit

Format	Frame Size	Frame Rate	Field Order	Video Codec	Bit Rate	Audio Channels
DV (SD)	720x480	59.94i	Lower	DV	25 CBR	2 channels, 32 kHz, 16 bit
DV (SD)	720x576	50i	Lower	DV	25 CBR	2 channels, 32 kHz, 16 bit

Adding media and creating clips

After you've previewed files to determine which media files you want to use in your project, you'll add clips to the timeline to indicate when each media file will be played.

For more information, see ["Previewing video" on page 65](#).



When you add the first video clip to a project, the timeline settings are automatically adjusted to match the media properties. For more information, see ["Using the Timeline Inspector" on page 14](#).

To change the magnification level of the timeline, you can drag the slider above the time ruler or click the Zoom Out  or Zoom In  buttons.

Snapping can help you align clips as you add them to the timeline. For more information, see ["Clip snapping" on page 115](#).


When a clip with audio and video streams is selected, you can use the Streams control in the Clip Inspector to choose which streams you want to use on the timeline. For more information, see ["Using the Clip Inspector" on page 128](#).

Adding clips to existing tracks

If you've already added tracks to your project, you can use the Media Browser to create clips on those tracks.

For more information, see ["Adding tracks to a project" on page 75](#).

1. Click the track header of the track where you want to add a clip.



2. Select the clips you want to use in the Media Browser.

For more information, see ["Finding media" on page 27](#).

 If you want to adjust mark in/out points before adding media, you can log mark in/out points in the Media Browser.

3. Click the Add to Timeline button  at the bottom of the Media Browser.

The selected files are added as clips to the end of the selected track, and the new clips are selected.

 If multiple clips are selected, they will be added to the track in the order they are displayed in the Media Browser.

You can also drag files from the Windows Explorer, Finder, or Media Browser to the timeline:

- If you drop a media file on an existing track, a clip will be created.
- If you drop a media file on a track's header, the new clip is created at the beginning of the timeline.
- If you drop a media file on a blank area of the timeline, a track will be created.

When you add spanned clips to the timeline, a single clip is created.

To change the magnification level of the timeline, you can drag the slider above the time ruler, roll the mouse wheel, or drag vertically with two fingers on a trackpad.

Any color adjustments that were applied in Catalyst Prepare are preserved when adding media to the Catalyst Edit timeline.

Adding clips and creating tracks

1. Use the Media Browser to find media files.
2. Select the media files you want to add to your project.

 If you want to adjust mark in/out points before adding media, you can log mark in/out points in the Media Browser. For more information, see ["Finding media" on page 27](#).

3. Click the Tools button  at the bottom of the Media Browser and choose Add selection as tracks from the menu.

A separate track is created for each selected clip, and a clip is created on each track for the clip. The clips will begin at the start of the timeline.



If multiple clips are selected, they will be added to the track in the order they are displayed in the Media Browser.

Hold Ctrl (Windows) or ⌘ (macOS) while dragging multiple clips from the Media Browser to the timeline to add the clips across tracks.

You can also drag files from the Windows Explorer, Finder, or Media Browser to the timeline. If you drop a media file on an existing track, a clip will be created. If you drop a media file on a blank area of the timeline, a track will be created.

When you add spanned clips to the timeline, a single clip is created.

To change the magnification level of the timeline, you can drag the slider above the time ruler, roll the mouse wheel, or drag vertically with two fingers on a trackpad.

Any color adjustments that were applied in Catalyst Prepare are preserved when adding media to the Catalyst Edit timeline.

Adding clips from a Catalyst Prepare library

Organize mode in Catalyst Prepare allows you to review your imported clips, group related clips in folders, view and edit metadata, and view mark points.

You can browse to a Catalyst Prepare library () in the Catalyst Edit Media Browser, or you can drag clips from Catalyst Prepare to the Catalyst Edit timeline:

1. Click the Organize button at the top of the Catalyst Prepare window .
2. The Library button  displays the current library. You can click the button to choose a different library or create a new library.

The library's media is displayed in the right side of the Catalyst Prepare  window .

3. Select the clips you want to use and drag them to the Catalyst Edit  timeline. Drop the clips where you want to create clips.

Playing media

The video preview is displayed above the timeline and displays a project's video output at the current cursor position during editing and playback. This window is also useful when editing frame by frame for synchronizing audio.

You can use the transport toolbar below the video to choose the playback mode, scrub the video, and control playback.

Previewing video

The video preview is displayed above the timeline and displays a project's video output at the current cursor position during editing and playback. This window is also useful when editing frame by frame for synchronizing audio.

You can also choose to display the video preview in a secondary window that you can position anywhere on your screen or on a secondary display. For more information, see "[Editing Catalyst Edit options](#)" on page 169.

If you want to use the primary display and secondary window to preview files from the Media Browser, you can use the Media Browser Settings button  to display the Media Browser Settings menu. For more information, see "[Finding media](#)" on page 27.


 The Video Preview window temporarily enters split-screen preview mode when trimming, roll-trimming, split-trimming, or slip-trimming clips. This temporary split-screen mode allows you to see both sides of the edit at once:



- When trimming the left edge of a clip, the left side of the preview displays the last frame from the previous clip (black if there is no previous clip), and the right side of the preview displays the first frame from the clip being trimmed.
- When trimming the right edge of a clip, the left side of the preview displays the last frame from the clip being trimmed, and the right side of the preview displays the first frame from the next clip (black if there is no next clip).
- When slip trimming the left or right edge of a clip, the left side of the preview displays the first frame from the clip being trimmed, and the right side of the preview displays the last frame from the clip being trimmed.

When splitting or trimming clips that contain audio, an invisible fade is applied at the edit to soften potentially harsh transitions.

Click the Preview button in the top-right corner of the video preview to choose a preview mode. Split-screen previews allow you to split the video preview and waveform/histogram/vectorscope monitor so you can see your affected and unaffected video at the same time.




-  Before: full-frame video is displayed in its original state.
 -  After: full-frame video is displayed in its color-corrected state.
 -  Split: a single frame is displayed in a split-screen view with the original video on the left and the color-corrected video on the right.
-  If you want to move the split location, hover over the preview frame. When the split point is displayed, you can drag the handles at the top of bottom of the screen to adjust where the preview is split:



-  2 Up: two full frames are displayed in a split-screen view with the original video on the left and the color-corrected video on the right.

Scaling the video preview

Click the magnifying glass to adjust the size of the video preview.



- Click Fit to scale the video to fill the Video pane.
- Click a preset to scale the video to a predefined magnification level.

When the level is below 100%, you can drag the blue rectangle to pan and adjust the visible portion of the frame.

- Drag the slider or click the **-** and **+** buttons to choose a custom zoom level.
- Click the thumbnail and roll your mouse wheel to zoom in or out.

Using the transport controls

The transport controls below the video preview allow you to control playback:

Button	Description
 Go to Start	Moves the playback position indicator to the beginning of the timeline.
 Previous Frame	Moves the playback position indicator one frame or field to the left.
 Play	Playback will start from the playback position indicator and continue until the the end of the file.
 Stop	Stops playback or recording and returns the cursor to its starting position.
 Next Frame	Moves the playback position indicator one frame or field to the right.
 Go to End	Moves the playback position indicator to the end of the timeline.
 Loop Playback	Plays only the area between the Mark In and Mark Out points in a continuous mode.

Button	Description
	For more information, see "Marking in and out points for playback" on page 73.

Using split-screen previews

You can use split-screen previews to preview your project with and without video effects. For more information, see ["Using video effects" on page 135.](#)

Click the Split-Screen Preview button in the top-right corner of the video preview to choose a preview mode. Split-screen previews allow you to split the video preview and waveform/histogram/vectorscope monitor so you can see your original and effected video at the same time.

-  Before: full-frame video is displayed in its original state.
-  After: full-frame video is displayed with effects applied.
-  Split: a single frame is displayed in a split-screen view with the original video on the left and the effected video on the right.

 If you want to move the split location, hover over the preview frame. When the split point is displayed, you can drag the handles at the top or bottom of the screen to adjust where the preview is split:



-  2 Up: two full frames are displayed in a split-screen view with the original video on the left and the effected video on the right.

Displaying overlays for safe areas and anamorphic masking

1. Click the  button to display the Video Settings menu.
2. Select the Show safe areas switch to enable safe area guides and a center point in the video preview.

When Show safe areas is enabled, Catalyst Edit displays rectangles marking 90% (action safe area) and 80% (title safe area) of the frame to serve as guidelines for framing.

3. Select the Mask to 2.39:1 switch to enable shading in the video preview to indicate how an anamorphic version of your content will appear.

Displaying waveform, histogram, and vectorscope monitors

The video preview includes a waveform monitor and histogram that you can use to monitor color values.

1. Click the  button to display the Video Settings menu.
2. Turn on the Waveform, Histogram, or Vectorscope switch to enable the monitor.

Waveform

The waveform monitor displays the luminance values (brightness or Y component) of your video signal. The monitor plots luminance values on the vertical axis and the width of the current frame on the horizontal axis.

You can use the buttons at the top of the waveform monitor to display overlaid () or separate () RGB waveforms and isolate colors .

Histogram

The histogram monitor displays the number of pixels that exist for each color intensity. The vertical axis represents the number of pixels, and the horizontal axis represents the RGB color range from 0 to 255.

You can use the buttons at the top of the histogram monitor to display overlaid () or separate () RGB histograms and isolate colors .

Vectorscope

The vectorscope monitor allows you to monitor the chroma values (color content) of your video signal. The monitor plots hue and saturation on a color wheel.

The vectorscope displays targets for broadcast-legal saturations of red (R), magenta (Mg), blue (B), cyan (Cy), green (G), and yellow (Yl). Individual colors in your video signal are displayed as dots in the vectorscope. A dot's distance from the center of the scope represents its saturation, and the angle of the line from the dot to the center of the scope represents its hue.

For example, if an image has a blue cast, the distribution of dots in the vectorscope will be concentrated toward the blue portion of the color wheel. If the image includes out-of-range blue values, the vectorscope display will extend beyond the blue target.

You can use the vectorscope to calibrate color between scenes. Without calibration, you may see noticeable color differences between scenes from multicamera shoots.

Click the Settings button  to open the Vectorscope Settings menu.


The Vectorscope Settings menu allows you to toggle a monochrome view of the scope, change the scale of the scope, adjust the brightness of the colors displayed in the scope, and adjust the brightness of the scope's guide (graticule).

 Use the 75% Scale setting when your source media uses 75% color bars, or use the 100% setting your source media uses 100% color bars.

Editing video effect parameters in the video preview

When you're editing video effects, a control point () is displayed in the video preview when you select a position parameter in the Inspector.

You can adjust the parameter's position by dragging the control point in the video preview or the Inspector:



When a plug-in includes support for interactive overlay controls in the video preview, you can click the Overlay button  in the Inspector to show or hide the overlay.

For more information, see ["Using video effects" on page 135](#).

Navigating the timeline

Drag the shuttle control to seek forward or backward from the play position indicator to find an edit point. As you drag toward the ends of the shuttle control, playback speed increases. Release the shuttle control to stop playback:




You can also press the J, K, or L keys to use the keyboard as a shuttle control.


 Press and hold K while pressing J or L to emulate a shuttle knob mode. Press K+J to scrub left or K+L to scrub right.

Item	Description
J	Scrub reverse mode. Press again to accelerate the playback rate.
K	Pause.
L	Scrub forward mode. Press again to accelerate the playback rate.

You can drag the play cursor to scrub the timeline:



You can drag the ruler to scroll the timeline:



Marking in and out points for playback

If you want to play only a portion of the timeline, you can select the portion of the video you want to play.

 You can also use the Preview pane in Media Browser mode to adjust mark points.

1. Click the timeline to set the play position indicator:



2. Click the Tools button  below the timeline and choose Mark in or press I.
3. Click the timeline to set the play position indicator.
4. Click the Tools button  below the timeline and choose Mark out or press O.

When you click the Play  button, playback will start from the playback position indicator and continue until the Mark Out position or the end of the file.

If you want to play the Mark In/Mark Out region in a continuous loop, select the Loop Playback button .

 Double-click a clip with the Edit, Slip, or Fade tool to select a clip and set the Mark In/Out region to match its length.

Double-click the fade between two clips with the Edit, Slip, or Fade tool to select a fade area and set the Mark In/Out region to match its length.

You can adjust mark in/out points by dragging the indicators above the timeline.

You can adjust the mark in/out region without changing its length by dragging the area between indicators above the timeline.

To reset mark in/out points, click the Tools button  below the timeline and choose Reset mark in/out points.

Track editing

Tracks are containers along the timeline where you arrange audio and video clips.

Clips sit on tracks to determine when a clip starts and stops, and multiple tracks are mixed together to produce your final output.

Adding tracks to a project

You can create empty tracks in a project to serve as placeholders for media that you will add to your project later, or you can create tracks when you add media to the project.

 Video tracks are composited together so that upper tracks obscure lower tracks. If a clip includes transparency, lower clips will be visible through the transparent areas.

Adding an empty track

Click the Track button  below the timeline and choose New from the menu. A new, empty track is created above the focus track.

 Press Ctrl+Shift+N (Windows) or Shift-⌘ -N (macOS).

Double-click below the last track header to create a new, empty track.

Adding a media file as a new track

1. Select the clips you want to use in the Media Browser.

For more information, see ["Finding media" on page 27](#).

2. Click the Media Tools button  at the bottom of the Media Browser below the timeline and choose Add selection as tracks from the menu to add the files to new tracks in your project. The new tracks are created at the bottom of the track list.

A separate track is created for each selected clip, and a clip is created on the timeline for each clip. The clips will begin at the start of the timeline, and the new clips are selected.



If multiple clips are selected, they will be added to the track in the order they are displayed in the Media Browser.

Hold Ctrl (Windows) or ⌘ (macOS) while dragging multiple clips from the Media Browser to the timeline to add the clips across tracks.

Deleting tracks

To delete a track, select the track and perform one of the following actions:

- Press Delete.
- Click the Track button  below the timeline and choose Delete from the menu.

Moving tracks

To move a track, drag its track header to a new location in the track list. An indicator is displayed to show you where the track will be moved.

When you release the mouse, the track and its clips will be moved.

Creating a picture-in-picture effect

The Picture in Picture effect allows you to resize and position clips for picture-in-picture compositing.

Creating the inner picture

1. Create two tracks in your project. For more information, see ["Adding tracks to a project" on page 75](#).
2. Add clips to your tracks:
 - The top track will contain the smaller, inner picture.
 - The bottom track will contain the background clip.

For more information, see ["Adding media and creating clips" on page 60](#).

3. Click the top track to select it.
4. Click the Track button  below the timeline and choose Picture in Picture. The controls for the Picture in Picture plug-in are displayed in the Track Inspector.


Editing picture in picture settings

1. Select the track that contains the top clip.
2. Click the Inspector button to show the Inspector pane.
3. In the Inspector, select the Track tab to view and edit settings for the Picture in Picture plug-in. Use the Picture in Picture plug-in to adjust the size and position of the top clip.

For more information, see ["Using the Track Inspector" on page 86](#).

Item	Description
Location	The drop-down list displays the current position of the video in the frame. Click to display an edit control you can use to position your video.

Item	Description
------	-------------



Adjusting box position

Drag the point in the edit control to set the position of your video in the frame. Double-click the point to reset it.

When you type values in the Dimensions tab, you can set an anchor point and specify the position of the box using X/Y coordinates. For example, click the top-right corner of the anchor control and use the coordinates 0.5000, 0.5000 to move the top-right corner of the box to the center of the control.

Adjusting box dimensions


You can drag the corners of the rectangle in the edit control or type values in the W and H edit boxes to set the size of the frame.

When you type values in the Dimensions tab, you can set the size of the box using W/H dimensions. Click the Lock button  to preserve the aspect ratio of the box so changing the width or height will automatically update the other value,

Adjusting box edges

You can drag the edges of the rectangle in the edit control or type values in the Edges tab to specify the position for each edge of the box.


Item	Description
	<p data-bbox="621 275 1365 348"> Drag a corner of the rectangle to preserve aspect ratio while resizing.</p> <p data-bbox="670 384 1390 457">Hold Shift while dragging the corners of the rectangle to resize and adjust aspect ratio.</p> <p data-bbox="670 489 1385 562">Hold Alt (Windows) or Option (macOS) to resize the rectangle from the center.</p> <p data-bbox="670 594 1406 667">Hold Ctrl (Windows) or ⌘ (macOS) to adjust the controls in fine increments.</p> <p data-bbox="670 699 1409 810">When a corner is selected, you can use the arrow keys to adjust the selected corner, or press Ctrl (Windows) or ⌘ (macOS) + the arrow keys to adjust in fine increments.</p> <p data-bbox="613 846 1252 877">Drag the edges of the rectangle to resize the rectangle.</p> <p data-bbox="621 909 1365 982"> Drag an edge of the rectangle to preserve aspect ratio while resizing.</p> <p data-bbox="670 1014 1382 1087">Hold Shift while dragging an edge to resize and adjust aspect ratio.</p> <p data-bbox="670 1119 1385 1192">Hold Alt (Windows) or Option (macOS) to resize the rectangle from the center.</p> <p data-bbox="670 1224 1406 1297">Hold Ctrl (Windows) or ⌘ (macOS) to adjust the controls in fine increments.</p> <p data-bbox="613 1329 1401 1402">Drag the center of the rectangle to move without resizing, or double-click the point to reset it.</p> <p data-bbox="621 1434 1390 1507"> Hold Shift while dragging to constrain to horizontal/vertical/45-degree movement.</p> <p data-bbox="670 1539 1406 1612">Hold Ctrl (Windows) or ⌘ (macOS) to adjust the controls in fine increments.</p> <p data-bbox="670 1644 1409 1717">When the rectangle is selected, you can copy the position of the rectangle to paste to another clip.</p>
Rotation	Type a value in the box or drag the slider to rotate the video in the frame.

Item	Description
Flip horizontal	Click to invert the video horizontally.
Flip vertical	Click to invert the video vertically.
Opacity	Type a value in the box or drag the slider to adjust the opacity of the top image. As you decrease the opacity, video from lower tracks will show through the foreground.
Shadow	
Type	Choose a setting from the drop-down list if you want to display a shadow over or behind the foreground image.
Offset	The drop-down list displays the current position of the shadow relative to the foreground image. Click to display an edit control you can use to position your shadow.
	
	<p>You can drag the point in the edit control or type values in the X and Y boxes to set the position of your shadow in the frame. Double-click the point to reset it.</p> <p> Hold Ctrl (Windows) or ⌘ (macOS) to adjust the point in fine increments.</p>
Rotation	Type a value in the box or drag the slider to rotate the shadow in the frame.
Scale	Type a value in the box or drag the slider to adjust the size of the shadow.
Blur	Type a value in the box or drag the slider to feather the edges of the shadow.
Opacity	Type a value in the box or drag the slider to adjust the opacity of the shadow. As you decrease the opacity, video from lower tracks will show through the foreground.
Glow	
Type	Choose a setting from the drop-down list if you want to display a glow effect over or behind the foreground image.


Item	Description
Amount	Type a value in the box or drag the slider to adjust the size of the glow effect.
Color/Second color	Click the color sample to display a color picker, where you can choose a color or type color values to set the shadow color. You can also adjust the transparency (alpha value) of the shadow.

Adjusting track controls

The controls in the track list allow you to adjust a track's volume, adjust track panning, and mute or solo a track.



When a track has multiple channels, separate controls are displayed for each channel. You can use the blue Volume fader to adjust the overall level of the track, and the orange Volume faders adjust each channel's contribution to the level of the track. For more information, see ["Working with multichannel audio" on page 158](#).




Click  to expand the track's channels.



Adjusting track volume

Drag the Volume fader to adjust the overall volume of the selected track. Double-click the center of the thumb to reset the fader. You can click the numeric value to type a new value:



 Dragging the Volume fader on the track header also adjusts the Volume fader in the Track Inspector. For more information, see ["Using the Track Inspector" on page 86](#).

Hold Ctrl (Windows) or ⌘ (macOS) to adjust the volume fader in fine increments.

When adjusting volume, remember to watch your audio meters. Because you are adding the volumes of all of the tracks together, it is easy to clip the audio output. Make sure that the meters never display the red Clip indication during playback. For more information, see ["Monitoring audio levels" on page 167](#).

The meter in the Track Inspector shows audio levels for the selected track. The meter in the activity pane at the top of the Catalyst Edit window shows the sum of all audio at the cursor position.

Muting a track

Click the  button to mute/unmute the selected audio track, or click the  button to mute a video track.

When a track is muted, it is excluded from the project output. You can enable the Mute button on additional tracks to add them to the mute group.

 Clicking the Mute button in the track header also updates the Mute button in the Track Inspector.

Soloing a track


Click the  button to solo/unsolo the selected track.

When a track is soloed, all unsoloed tracks are effectively muted. Click the  button on additional tracks to add them to the solo group. To remove a track from the solo group, click its  button again.

 Clicking the Solo button in the track header also updates the Solo button in the Track Inspector.

Panning a track


Drag the Pan knob to control the position of the track in the stereo field: dragging to the down or to the left will place the track in the left speaker more than the right, and dragging up or to the right will place the track in the right speaker. Double-click the knob to reset panning to the center.



Dragging the Pan knob on the track header also adjusts the Pan knob in the Track Inspector.

 The Track pan knob is not displayed for tracks that are assigned to a mono output or that contain multichannel clips. When a track contains multichannel clips, use the Audio Channel controls to pan each channel.

If you want to change the panning model that is used for the track, click the Pan mode button in the Track Inspector and choose a setting from the menu:




For more information, see ["Using the Track Inspector" on page 86](#).

Using the Track Inspector


In the Inspector , select the Track tab to view and edit settings for the selected track.

 Click a track's header to select it, and the Track tab is displayed automatically if the Inspector is visible:



Summary

Type a value in the Name box to set the name of the selected track. The name you type here will be displayed in the track header:



When Ripple is first enabled, ripple edits are enabled for all tracks. If you want to turn ripple editing on or off for a track, use the Ripple sync switch.


 The Ripple sync switch is available only when the Ripple button  above the timeline is enabled.

Audio Output

Each track in your project supports two audio channels, and each clip in your project supports multichannel audio. For more information, see ["Working with multichannel audio" on page 158](#).

The Audio Output controls in the Track Inspector allow you to adjust the overall level of the track and control each channel's contribution to the stereo track.

Item	Description
Track volume	Click the value and type a new value or drag the fader adjust the overall volume of the selected track. Double-click the center of the thumb to reset the fader.



 Dragging the Volume fader in the Track Inspector also adjusts the Volume fader on the track header. For more information, see ["Adjusting track controls" on page 82](#).


Hold Ctrl (Windows) or ⌘ (macOS) to adjust the volume fader in fine increments.

When adjusting volume, remember to watch your audio meters. Because you are adding the volumes of all of the tracks together, it is easy to clip the audio output. Make sure that the meters never display the red Clip indication during playback. For more information, see ["Monitoring audio levels" on page 167](#).

The meter in the Track Inspector shows audio levels for the selected track. The meter in the activity pane at the top of the Catalyst Edit window shows the sum of all audio at the cursor position.

Track pan	Drag the knob to control the position of the track in the stereo field: dragging to the down or to the left will place the audio in the left speaker more than the right, and dragging up or to the right will place the audio in the right speaker. Double-click the knob to reset panning to the center. Dragging the Pan knob in the Track Inspector also adjusts the Pan knob on the track header.
-----------	---

Item	Description
	 The Track pan knob is not displayed for tracks that are assigned to a mono output or that contain multichannel clips. When a track contains multichannel clips, use the Audio Channel controls to pan each channel.
Pan mode	Click the Pan mode button and choose a setting from the menu to choose the panning model that is used for the track:



- Add: This mode is most useful for panning stereo files. As you pan across the stereo field, the stereo image appears to move across the speakers. As you pan toward either side, the signal from the opposite channel is added to the channel you are panning toward until at the extreme both channels are sent to a single channel at full volume.

This mode uses a linear panning curve.


- Constant power: This mode is most useful for panning monaural source material. In this mode, sound will maintain its volume when you pan across channels.

If you pan a stereo file 100% R, only the right channel of your media file is played, and this channel is sent to both output channels. If you continue to pan to the left, the left channel is gradually added to the output, and the right channel is gradually faded out until only the left channel will be heard through both output channels when the slider is at 100% L.

- 3 dB notch: This mode can help you adjust the relative signal levels of the channels in stereo source material. A -3 dB cut is applied when you're panned to the center. As you pan from the center to either side, the opposite channel begins at -3 dB and decays to -infinity. The signal in the side you are panning toward progresses from -3 dB

Item	Description
	<p>to 0 dB.</p> <p>This panning mode uses a linear panning curve.</p> <ul style="list-style-type: none"> 6 dB notch: This mode can help you adjust the relative signal levels of the channels in stereo source material. A -6 dB cut is applied when you're panned to the center. As you pan from the center to either side, the opposite channel begins at -6 dB and decays to -infinity. The signal in the side you are panning toward progresses from -6 dB to 0 dB. <p>This panning mode uses a linear panning curve.</p> <p> For example, when using the 3 dB notch or 6 dB notch settings, when you pan fully right, the right channel is played at 0 dB and the left channel is not audible. As you pan to the center, each channel is attenuated to the specified center value (-3 dB or -6 dB). As you pan to the left, the left channel is played at 0 dB, and the right channel is not audible.</p>
Mute	<p>Click  to mute/unmute the selected track.</p> <p>When a track is muted, it is excluded from the audio mix. You can enable the  button on additional tracks to add them to the mute group.</p> <p> Clicking the Mute button in the Track Inspector also updates the Mute button on the track header.</p>
Solo	<p>Click  to solo/unsolo the selected track.</p> <p>When a track is soloed, all unsoloed tracks are effectively muted. Click the  button on additional tracks to add them to the solo group. To remove a track from the solo group, click its  button again.</p> <p> Clicking the Solo button in the Track Inspector also updates the Solo button on the track header.</p>
<p>The following controls are displayed only when a track contains multichannel clips. For more information, see "Working with multichannel audio" on page 158,</p>	
Channel volume	<p>Drag the fader to adjust the volume of the selected channel. Double-click the center of the thumb to reset the fader. You can double-click the numeric value to type a new value:</p>

Item	Description
------	-------------



 Dragging the Volume fader in the Track Inspector also adjusts the Volume fader on the track header. For more information, see ["Adjusting track controls" on page 82.](#)

Hold Ctrl (Windows) or ⌘ (macOS) to adjust the volume fader in fine increments.

When adjusting volume, remember to watch your audio meters. Because you are adding the volumes of all of the tracks together, it is easy to clip the audio output. Make sure that the meters never display the red Clip indication during playback. For more information, see ["Monitoring audio levels" on page 167.](#)

The meter in the Track Inspector shows audio levels for the selected channel. The meter in the activity pane at the top of the Catalyst Edit window shows the sum of all audio at the cursor position.


Channel pan	Drag the knob to control the position of the channel in the stereo field: dragging to the down or to the left will place the audio in the left speaker more than the right, and dragging up or to the right will place the audio in the right speaker. Double-click the knob to reset panning to the center.
-------------	--

Dragging the Pan knob in the Track Inspector also adjusts the Pan knob on the track header.

 The Channel pan knob is not displayed for channels that are assigned to a mono output.

Pan mode	Click the Pan mode button and choose a setting from the menu to choose the panning model that is used for the channel:
----------	--

Item	Description
------	-------------



Please see ["Pan mode" on page 88](#) for descriptions of the available pan modes.

Mute	Click  to mute/unmute the selected channel.
------	--

When a channel is muted, it is excluded from the audio mix. You can enable the  button on additional channels to add them to the mute group.

 Clicking the Mute button in the Track Inspector also updates the Mute button on the track header.

Solo	Click  to solo/unsolo the selected channel.
------	--

When a channel is soloed, all unsoloed channels are effectively muted. Click the  button on additional channels to add them to the solo group. To remove a channel from the solo group, click its  button again.

 Clicking the Solo button in the Track Inspector also updates the Solo button on the track header.

Video Effects

When the selected track has effects applied to it, you can use the Video Effects controls to control the settings for each effect. For more information, see ["Adding effects to a track" on page 137](#).

Click the Overlay button  to show or hide a plug-in's interactive overlay controls in the video preview (when available).

Click the Mute button  to bypass a plug-in without removing it from the chain.

Click the Delete button  to remove a plug-in from the chain.

Drag a plug-in's heading to change its position in the plug-in chain.

Click the toggle arrow to show or hide each plug-in's controls.

When you select a position parameter in the Inspector, a control point () is displayed in the video preview. You can adjust the parameter's position by dragging the control point in the video preview or the Inspector:



Adjusting timeline settings

Click the Timeline settings button  above the timeline to display the Timeline Settings menu, where you can adjust various settings for the project timeline.

 When you add the first video clip to a project, the timeline settings are automatically adjusted to match the media properties. For more information, see ["Adding media and creating clips" on page 60](#).

Adjusting track height

Adjusting track height allows you to gain a wider view of your project or focus on a specific track.

1. Click the Timeline settings button  above the timeline.
2. Drag the Track height slider to the left to make all tracks shorter, or drag to the right to make all tracks taller.

 If you want to adjust the size of the video preview to increase or decrease the size of the timeline, drag the splitter between the video preview and timeline.

Showing or hiding the marker ruler

1. Click the Timeline settings button  above the timeline.
2. Click the Marker ruler switch to show or hide the marker ruler.

For more information, see ["Using markers" on page 118](#).

Clip editing

Clips are containers that represent an occurrence of a media file on the Catalyst Edit timeline. A clip can represent an entire media file or a portion of it. A single media file can be used repeatedly to create any number of different clips, since each clip can be trimmed independently. A clip's position on the timeline determines when it will be played back in your project.

Editing tools

The Tools button below the timeline allows you to select the active editing tool.

Click the button and choose a tool from the menu.

Tool	Description
	<p>Edit Tool: Use the Edit Tool to select, trim, and move clips on the timeline.</p> <p>For more information, see "Trimming clips" on page 102 and "Moving clips" on page 99.</p> <p> Press E when the timeline has focus to switch to the Edit Tool.</p> <p>Hold Shift while dragging the end of the audio or video stream with the Edit Tool to enable Edit Streams mode temporarily. For more information, see "Stream editing (L-J cuts and rolls)" on page 106.</p> <p>Hold E to switch to the Edit Tool temporarily. When you're finished editing, release the E key, and the previous editing tool will be restored.</p>
	<p>Roll Trim Tool: Use the Roll Trim Tool to trim the edges of two adjacent clips simultaneously.</p> <p>For more information, see "Trimming clips" on page 102.</p> <p> Press R when the timeline has focus to switch to the Roll Trim Tool.</p> <p>Hold Shift while dragging the end of the audio or video stream with the Roll Trim Tool to enable Edit Streams mode temporarily. For more information, see "Stream editing (L-J cuts and rolls)" on page 106.</p> <p>Hold R to switch to the Roll Trim Tool temporarily. When you're finished editing, release the R key, and the previous editing tool will be restored.</p>

Tool	Description
	<p>Select Tool: Use the Select Tool to select clips.</p> <p>For more information, see "Selecting clips and positioning the cursor" on page 98.</p> <p> Press C when the timeline has focus to switch to the Select Tool.</p> <p>Hold C to switch to the Select Tool temporarily. When you're finished selecting clips, release the C key, and the previous editing tool will be restored.</p>
	<p>Slip Tool: Use the Slip Tool to select, slip, and slip trim clips.</p> <p>For more information, see "Clip editing" on page 108.</p> <p> Press P when the timeline has focus to switch to the Slip Tool.</p> <p>Hold P to switch to the Slip Tool temporarily. When you're finished editing, release the P key, and the previous editing tool will be restored.</p>
	<p>Split Trim Tool: Use the Split Trim Tool to split and trim clips by clicking where you want to split and dragging to trim the resulting clip. If you click without dragging, the clip is split at the point you click.</p> <p>For more information, see "Trimming clips" on page 102.</p> <p> Press T when the timeline has focus to switch to the Split Trim Tool.</p> <p>Hold T to switch to the Split Trim Tool temporarily. When you're finished editing, release the T key, and the previous editing tool will be restored.</p>
	<p>Fade Tool: Use the Fade Tool to adjust the level or opacity of a clip and adjust fade in/out curves.</p> <p>For more information, see "Clip fades" on page 122.</p> <p> Press F when the timeline has focus to switch to the Fade Tool.</p> <p>Hold F to switch to the Fade Tool temporarily. When you're finished editing, release the F key, and the previous editing tool will be restored.</p>
	<p>Envelope Tool: Use the Envelope Tool to automate volume over the length of the clip.</p> <p>For more information, see "Clip volume automation" on page 123.</p>

Tool	Description
	<p data-bbox="428 275 1263 310"> Press V when the timeline has focus to switch to the Envelope Tool.</p> <p data-bbox="480 342 1406 457">Hold Shift while dragging the end of the audio or video stream with the Envelope Tool to enable Edit Streams mode temporarily. For more information, see "Stream editing (L-J cuts and rolls)" on page 106.</p> <p data-bbox="480 489 1398 558">Hold V to switch to the Envelope Tool temporarily. When you're finished editing, release the V key, and the previous editing tool will be restored.</p>

Selecting clips and positioning the cursor

Selecting data and positioning the cursor are the first steps in a variety of editing tasks.

 You can select clips with any of the editing tools, but using the Select tool helps ensure that clips cannot be moved during selection. For more information, see ["Editing tools" on page 95](#).

Press Ctrl+A (Windows) or ⌘ -A (macOS) to select all clips.

Selecting a single clip

Click a clip to select it and deselect other selected clips.

 If you want to select a clip without moving the cursor, click the clip header:



If you want to deselect all selected clips, click a blank area of the timeline.

Selecting multiple adjacent clips

Hold the Shift key and click the first and last clip that you want to select. All clips between the first and last clip you clicked are selected.

Selecting multiple nonadjacent clips

1. Click the Tools button below the timeline and select the Select Tool .

 Hold Ctrl (Windows) or ⌘ (macOS) while clicking clips with the Edit Tool , Roll Trim

, Slip Tool , or Fade Tool .


2. Click the clips you want to select. The selected clips are highlighted.

To deselect a clip, simply click it again.

Positioning the cursor

To set the cursor position, click in the timeline or time ruler. The cursor moves to the position you click, and the cursor position is displayed below the video preview.

 If you want to position the cursor without changing your clip selection, you can drag the cursor or playhead:



Press Up Arrow/Down Arrow to move the cursor to the previous/next clip on the selected track (when timeline has focus).

Moving clips

A clip's position on the timeline determines where it will be played in your project.

Dragging a clip to a new position

Dragging is the simplest way to move clips in your project. You can drag a clip so it occurs earlier or later in your project, or you can drag a clip to another track.

1. Click the Tools button below the timeline and select the Edit Tool .
2. Select the clips you want to move. For more information, see ["Selecting clips and positioning the cursor" on page 98](#).
3. Drag the clip to the position where you want it to be played.

If ripple mode is enabled, all subsequent clips will ripple automatically. For more information, see ["Ripple edits" on page 114](#).

 Ripple mode is temporarily suspended when dragging a clip to a different track.

Drag a clip to a blank area of the timeline to create a new track.

4. Release the mouse button.

Moving multiple clips


1. Click the Tools button below the timeline and select the Edit Tool .
2. Select the clips you want to move. For more information, see ["Selecting clips and positioning the cursor" on page 98](#).
3. Drag the clips to the position where you want them to be played. If ripple mode is enabled, all subsequent clips will ripple automatically. For more information, see ["Ripple edits" on page 114](#).
4. Release the mouse button.

Creating crossfades

When you overlap two clips, a crossfade is applied to transition between the two clips.

1. Click the Tools button below the timeline and select the Edit Tool .
2. Select the clips you want to move. For more information, see ["Selecting clips and positioning the cursor" on page 98.](#)
3. Drag the clip so it overlaps another clip. If ripple mode is enabled, all subsequent clips will ripple automatically. For more information, see ["Ripple edits" on page 114.](#)

Fades are applied in the overlapping area.



Creating contained clips

When a shorter clip is placed in the middle of another clip, the first clip plays, a cut transitions to the second clip, and a cut transitions back to the first clip.

1. Click the Tools button below the timeline and select the Edit Tool .
2. Select a clip. For more information, see ["Selecting clips and positioning the cursor" on page 98.](#)
3. If needed, trim the shorter clip that you want to use as a contained clip. For more information, see ["Trimming clips" on page 102.](#)
4. Drag the shorter clip on top of the longer clip. If ripple mode is enabled, all subsequent clips will ripple automatically. For more information, see ["Ripple edits" on page 114.](#)

When you play your project, the first clip plays, a cut transitions to the second clip, and a cut transitions back to the first clip. Fades are not applied to contained clips.

Trimming clips

Trimming a clip allows you to control which part of the clip is played on the timeline.

 The Video Preview window temporarily enters split-screen preview mode when trimming, roll-trimming, split-trimming, or slip-trimming clips. This temporary split-screen mode allows you to see both sides of the edit at once:



- When trimming the left edge of a clip, the left side of the preview displays the last frame from the previous clip (black if there is no previous clip), and the right side of the preview displays the first frame from the clip being trimmed.
- When trimming the right edge of a clip, the left side of the preview displays the last frame from the clip being trimmed, and the right side of the preview displays the first frame from the next clip (black if there is no next clip).
- When slip trimming the left or right edge of a clip, the left side of the preview displays the first frame from the clip being trimmed, and the right side of the preview displays the last frame from the clip being trimmed.

When splitting or trimming clips that contain audio, an invisible fade is applied at the edit to soften potentially harsh transitions.

Trimming the start or end of a clip

1. Click the Tools button below the timeline and select the Edit Tool .

 Hold E to switch to the Edit Tool temporarily. When you're finished editing, release the E key, and the previous editing tool will be restored.

2. Drag either end of a clip to change its starting or ending point. The media on the timeline does not move, but the start or end point of the clip will change with the clip edge.

If ripple mode is enabled, all subsequent clips will ripple automatically. For more information, see ["Ripple edits" on page 114](#).

If snapping is enabled, the clip edge will snap to available snap points as you drag it. For more information, see ["Clip snapping" on page 115](#).



 If you drag the end of the clip past the length of the source clip, the clip is bound to the clip length.

If you trim a clip until its length is zero, the clip is deleted from the timeline.

If multiple clips are selected before you start trimming, the clip you trim remains selected, and the other clips are deselected.

To trim small clips, you may need to zoom in to the timeline.

To change the magnification level of the timeline, you can drag the slider above the time ruler or click the Zoom Out  or Zoom In  buttons.

Split trimming a clip

1. Click the Tools button below the timeline and select the Split Trim Tool .

 Hold T to switch to the Split Trim Tool temporarily. When you're finished editing, release the T key, and the previous editing tool will be restored.

2. Click a clip and drag to split the clip at the point you click and trim the clip in the direction you drag (eraser mode).

If ripple mode is enabled, all subsequent clips will ripple automatically. For more information, see ["Ripple edits" on page 114](#).

If snapping is enabled, the clip edge will snap to available snap points as you drag it. For more information, see ["Clip snapping" on page 115](#).

 If you drag the end of the clip past the length of the source clip, the clip is bound to the clip length.

If you trim a clip until its length is zero, the clip is deleted from the timeline.

Slip-trimming a clip

1. Click the Tools button below the timeline and select the Slip Tool .

 Hold P to switch to the Slip Tool temporarily. When you're finished editing, release the P key, and the previous editing tool will be restored.

2. Drag the right or left edge of a clip.

As you drag the clip edge, the opposite edge of the clip will remain fixed, trimming the media from the edge you drag.

If ripple mode is enabled, all subsequent clips will ripple automatically. For more information, see ["Ripple edits" on page 114](#).

If snapping is enabled, the clip edge will snap to available snap points as you drag it. For more information, see ["Clip snapping" on page 115](#).

Trimming adjacent clips (roll trim)

1. Click the Tools button below the timeline and select the Roll Trim Tool .

 Hold R to switch to the Roll Trim Tool temporarily. When you're finished editing, release the R key, and the previous editing tool will be restored.

2. Drag the edge between two adjacent clips. The edges of the clips are trimmed simultaneously in the direction you drag.


If snapping is enabled, the clip edge will snap to available snap points as you drag it. For more information, see ["Clip snapping" on page 115](#).

 If you drag the end of the clip past the length of the source clip, the clip is bound to the clip length.

If you trim a clip until its length is zero, the clip is deleted from the timeline.

As you drag, the video preview switches to a split-screen preview to allow you to see the


frame on either side of the edit:




Stream editing (L-J cuts and rolls)

Stream editing allows you to trim a clip's audio and video separately while still keeping both streams combined in a single timeline clip so that you can quickly and easily create J and L cuts.

- In an L cut or roll, the audio from the first clip continues after the video has been trimmed, allowing the user to see the new scene before hearing its audio:




- In a J cut or roll, the audio from the second clip begins before the video, allowing the user to hear the new scene's audio before seeing the video.



1. Click the Tools button below the timeline and select the Edit Tool , Roll Trim Tool , or Envelope Tool .
-  Hold E to switch to the Edit Tool temporarily. When you're finished editing, release the E key, and the previous editing tool will be restored.
2. Select the Edit Streams button  below the timeline (or press Shift+E).
-  Press and hold Shift before dragging the end of the audio or video stream with the Edit Tool, Roll Trim Tool, or Envelope Tool to enable Edit Streams mode temporarily.

3. Drag either end of a clip's audio or video stream to change its starting or ending point. The media on the timeline does not move, but the start or end point of the stream will change with the clip edge.

If snapping is enabled, the stream edge will snap to available snap points as you drag it. For more information, see ["Clip snapping" on page 115](#).




- 💡 If you drag the end of the clip past the length of the source clip, the clip is bound to the clip length.

If multiple clips are selected before you start trimming, the clip you trim remains selected, and the other clips are deselected.

To trim small clips, you may need to zoom in to the timeline.

To change the magnification level of the timeline, you can drag the slider above the time ruler or click the Zoom Out 🔍 or Zoom In 🔍 buttons.

If you want to move a clip, drag its header. If ripple mode is enabled, all subsequent clips will ripple automatically. For more information, see ["Ripple edits" on page 114](#).



Splitting clips

Splitting a clip allows you to adjust a small part of a clip or break a single clip into multiple sections that you can edit independently.

1. Click the timeline to position the cursor where you want to split the clip. You can use any of the available editing tools.

For more information, see ["Editing tools" on page 95](#).

2. Select the clips you want to split.
3. Click the Clip button  below the timeline and choose Split from the menu (or press S).

The clip is split at the cursor position, and the clip to the right of the split point is selected.



If no clips are selected, the clips located at the current cursor position will be split throughout all of the tracks.

When splitting or trimming clips that contain audio, an invisible fade is applied at the edit to soften potentially harsh transitions.

Slipping clips

To help you picture what happens when you slip clips, think of a clip as a window to a media file. The window can display the entire media file or a small section.

When the window displays only a portion of the media file, you can move either the window or the underlying media to adjust the media that is played by a clip: when you slip a clip, your clip maintains its place on the timeline, but the media file moves in the direction you drag.


- 💡 The Video Preview window temporarily enters split-screen preview mode when slipping or slip-trimming clips. This temporary split-screen mode allows you to see both sides of the edit at once:



- When slip trimming the left or right edge of a clip, the left side of the preview displays the first frame from the clip being trimmed, and the right side of the preview displays the last frame from the clip being trimmed.
- When slipping a clip, the left side of the preview displays the first frame from the clip being slipped, and the right side of the preview displays the last frame from the clip being slipped.

Slipping a clip

1. Click the Tools button below the timeline and select the Slip Tool  .
 - 💡 Hold P to switch to the Slip Tool temporarily. When you're finished editing, release the P key, and the previous editing tool will be restored.
2. Drag the clip. The slip cursor is displayed:



As you drag the clip, the contents of the clip shift, but the clip will not move. You can use this technique when you want to maintain a clip's length and position, but have the clip play a different section of the source media file.



Press Esc when dragging to cancel a slip.

Slipping is available only when a clip is shorter than its source media. If you want to slip a clip that represents a full clip, trim the clip first or use slip-trim. For more information, see ["Trimming clips" on page 102](#).

Slip-trimming a clip

1. Click the Tools button below the timeline and select the Slip Tool  .



Hold P to switch to the Slip Tool temporarily. When you're finished editing, release the P key, and the previous editing tool will be restored.

2. Drag the right or left edge of a clip.

As you drag the clip edge, the opposite edge of the clip will remain fixed, trimming the media from the edge you drag.

If ripple mode is enabled, all subsequent clips will ripple automatically. For more information, see ["Ripple edits" on page 114](#).

If snapping is enabled, the clip edge will snap to available snap points as you drag it. For more information, see ["Clip snapping" on page 115](#).


Cropping clips

The Crop effect allows you to reframe the viewable area of a clip.

1. Select the clip you want to edit.
2. Click the Clip button  below the timeline and choose Crop from the menu.
3. In the Inspector, use the Clip tab to view and edit crop settings for the selected clip.

For more information, see ["Using the Clip Inspector" on page 128](#).

Item	Description
Position	<p>The drop-down list displays the current position of the video in the frame. Click to display an edit control you can use to frame your video.</p> <p> Click Match Timeline Aspect to adjust the Position controls to match the output frame aspect from the Timeline Inspector.</p>



Adjusting box position

Drag the point in the edit control to set the position of your video in the frame. Double-click the point to reset it.

When you type values in the Dimensions tab, you can set an anchor point and specify the position of the box using X/Y coordinates. For example, click the top-right corner of the anchor control and use the coordinates 0.5000, 0.5000 to move the top-right corner of the box to the center of the control.

Adjusting box dimensions

You can drag the corners of the rectangle in the edit control or type values in the W and H edit boxes to set the size of the frame.

When you type values in the Dimensions tab, you can set the size of the box using W/H dimensions. Click the Lock button  to preserve the aspect ratio of the box so changing the width or height will automatically update the

Item	Description
	<p>other value.</p> <p>Adjusting box edges</p> <p>You can drag the edges of the rectangle in the edit control or type values in the Edges tab to specify the position for each edge of the box.</p> <p> Drag a corner of the rectangle to preserve aspect ratio while resizing.</p> <p>Hold Shift while dragging the corners of the rectangle to resize and adjust aspect ratio.</p> <p>Hold Alt (Windows) or Option (macOS) to resize the rectangle from the center.</p> <p>Hold Ctrl (Windows) or ⌘ (macOS) to adjust the controls in fine increments.</p> <p>When a corner is selected, you can use the arrow keys to adjust the selected corner, or press Ctrl (Windows) or ⌘ (macOS) + the arrow keys to adjust in fine increments.</p> <p>Drag the edges of the rectangle to resize the rectangle.</p> <p> Drag an edge of the rectangle to preserve aspect ratio while resizing.</p> <p>Hold Shift while dragging an edge to resize and adjust aspect ratio.</p> <p>Hold Alt (Windows) or Option (macOS) to resize the rectangle from the center.</p> <p>Hold Ctrl (Windows) or ⌘ (macOS) to adjust the controls in fine increments.</p> <p>Drag the center of the rectangle to move without resizing, or double-click the point to reset it.</p> <p> Hold Shift while dragging to constrain to horizontal/vertical/45-degree movement.</p> <p>Hold Ctrl (Windows) or ⌘ (macOS) to adjust the controls in fine increments.</p> <p>When the rectangle is selected, you can copy the position of the rectangle to paste to another clip.</p>

Item	Description
Angle	Type a value in the box or drag the slider to rotate the crop frame.
Flip horizontal	Click to invert the video horizontally.
Flip vertical	Click to invert the video vertically.
Zoom	When Zoom is on, the output frame aspect ratio matches the crop rectangle you set using the Position rectangle, allowing the cropped clip to fill the output frame. When Zoom is off, the video is cropped using a transparent background.

Cutting, copying, and pasting clips

Catalyst Edit allows you to cut, copy, and paste clips them into new positions on the timeline. You can paste a clip within the same track or to a new track.

Cutting clips

1. Select the clips you want to cut. For more information, see ["Selecting clips and positioning the cursor" on page 98.](#)
2. Click the Clip button  below the timeline and choose Cut from the menu or press Ctrl+X (Windows) or ⌘ +X (macOS).

The clip and its properties are removed from the timeline and moved to the clipboard. For more information, see ["Using the Clip Inspector" on page 128.](#)

Copying clips

1. Select the clips you want to copy. For more information, see ["Selecting clips and positioning the cursor" on page 98.](#)
2. Click the Clip button  below the timeline and choose Copy from the menu or press Ctrl+C (Windows) or ⌘ +C (macOS).

The clip and its properties are copied to the clipboard. For more information, see ["Using the Clip Inspector" on page 128.](#)

-  While dragging a clip on the timeline, press and hold Ctrl (Windows) or ⌘ (macOS) to create a copy of the clip where you drop it.

Pasting clips

1. Stop playback.
2. Select the track where you want to paste.
3. Click the timeline to position the cursor where you want to paste the clips.
4. Click the Clip button  below the timeline and choose Paste from the menu or press Ctrl+V (Windows) or ⌘ +V (macOS).
5. The clips from the clipboard are pasted starting at the cursor position in the focus track (the last track selected when multiple tracks are selected). If necessary, tracks will be added to accommodate the clipboard tracks.

The pasted clip retains the properties of the clip you copied. For more information, see ["Using the Clip Inspector" on page 128](#).

Pasted clips will sit on top of other clips in the track if they overlap. To make space for pasted clips, you can split the clip at the cursor position and select the Ripple button  above the timeline before pasting. For more information, see ["Splitting clips" on page 108](#) and ["Ripple edits" on page 114](#).

Deleting clips

Deleting a clip removes it from the track without modifying the media file on your computer.

1. Select the clips you want to delete. For more information, see ["Selecting clips and positioning the cursor" on page 98](#).

 Hold Shift while clicking to select a range of clips.

Hold Ctrl (Windows) or ⌘ (macOS) to select multiple, nonadjacent clips.

2. Click the Clip button  below the timeline and choose Delete from the menu.

Ripple edits

When the Ripple button  above the timeline is enabled, clips and markers that occur later on a track are shifted automatically when any of the following edits are performed:

- Adjusting a clip's length by trimming or slip-trimming.
- Moving clips.
- Deleting clips.
- Cutting clips.
- Pasting clips.

When Ripple is not enabled, clip edits will not affect other clips and markers on the timeline.

Turning off ripple synchronization for individual tracks

When Ripple is first enabled, ripple edits are enabled for all tracks. Edit operations on a any track ripple downstream clips on all tracks.

If you want to turn ripple editing off for a track, use the Ripple sync switch on the Track Inspector. For more information, see ["Using the Track Inspector" on page 86](#).

 The Ripple sync switch is available only when the Ripple button  above the timeline is enabled.

When Ripple sync is turned off, an  indicator is displayed in the track header, and a striped background is displayed in the timeline to indicate that you can move clips on a track freely even when ripple editing is selected:



Clip snapping


Click the Snap button  above the timeline to turn snapping on or off in the main timeline.

Snapping helps you align items along the timeline when you add clips, move clips, trim clips, or position the cursor. As you drag clips or markers, an indicator is displayed across the height of the timeline to show snap points.

 When snapping is enabled, you can hold the Shift key to temporarily override snapping.

When snapping is not enabled, you can hold the Shift key to temporarily enable snapping.

If you drag to a snap point that does not occur on a frame boundary when Quantize to frames is enabled, the snap indicator is displayed as a dashed line to indicate that the snap point will be quantized to the nearest frame boundary. For more information, see ["Quantize to frames" on page 117](#).



Turning snapping on or off

Click the Snap button  above the timeline to turn snapping on or off in the main timeline.

When snapping is enabled, clips and markers will snap to the following points on the timeline:

- The cursor (when playback is stopped).
- Markers.
- Clip edges on the same track.
- Clips on different tracks (when Snap to all clips is enabled).

Snapping to clips on other tracks

When snapping is enabled, you can also choose to have elements in the timeline snap to the ends of clips on other tracks.

Click the Editing Behaviors button  and turn on the Snap to all clips switch: clips, the cursor, and markers will snap to clip edges on any track, and the button is displayed as .

When Snap to all clips is off, clips will snap to clip edges only on their own tracks, and the button is displayed as .

Quantize to frames

Edits that do not occur on frame boundaries can produce an undesirable visual result. For example, if you split two clips and move them together to create a cut, splits that are not at frame boundaries can produce a short dissolve in your rendered video.


Click the Editing Behaviors button **•••** above the timeline and select Quantize to frames to force edits to occur on project frame boundaries.

This setting is independent of clip snapping. For more information, see ["Clip snapping" on page 115](#).

When Quantize to frames is turned on, the following actions will always occur on frame boundaries:

- Moving video clips
 -  If Quantize to Frames is on while dragging an audio clip and the selection group contains video, the movement is quantized so the first video clip is quantized (instead of the audio clip).

Audio-only clips are not quantized.
- Splitting and trimming clips
 -  If you drag to a snap point that does not occur on a frame boundary when Quantize to Frames is enabled, the snap indicator is displayed as a dashed line to indicate that the snap point will be quantized to the nearest frame boundary. For more information, see ["Clip snapping" on page 115](#).



Using markers

Markers can be used to indicate points of interest in projects or to make notes in the project.

Adding a marker

1. Click to select a track and position the timeline cursor where you want to add the marker.
2. Click the Add button  below the timeline and choose Marker. The marker  is created on the marker ruler above the timeline.


 Double-click an empty area of the marker ruler to add a marker quickly.

Selecting a marker

Click a marker tag  to select it.

Naming a marker

1. Double-click (or right-click) the marker you want to edit. The Marker popup is displayed.
2. Type a name in the Name box. The name in the marker ruler is updated to use the new name.



Changing a marker's color

1. Double-click (or right-click) the marker you want to edit. The Marker popup is displayed.
2. Click a color swatch. The marker tag is updated to use the new color.

Deleting a marker

1. Double-click (or right-click) the marker you want to delete. The Marker popup is displayed.
2. Click the Delete button.

Moving a marker

Drag the marker tag  to a new location.

-  When snapping is enabled and Snap to all clips is turned on, markers will snap to clip edges as you drag them. Hold Shift while dragging to temporarily override the current snapping setting. For more information, see ["Clip snapping" on page 115](#).

Showing or hiding the marker ruler


1. Click the Timeline settings button  above the timeline.
2. Drag the Marker ruler slider to the left to show the marker ruler, or drag to hide it.

Nested timelines

Nesting allows you to add a Catalyst Edit subordinate timeline to another project. Nesting can help you organize a timeline or create other effects:

- Create a single element – such as a lower-third graphic or watermark – that you can use in multiple timeline locations or projects.
- Create a complex composited element that you can use as a single media object in the timeline.
- Create a separate timeline for each scene in a video and nest those timelines in a master video project.
- Add a Catalyst Prepare storyboard to the timeline.
- Add a Catalyst Browse clip list to the timeline.

Clips with nested timelines are displayed in green:



Creating a nested timeline

1. Select the clips you want to include in your nested timeline. The selection must contain a contiguous range of clips (no spaces between clips). For more information, see ["Selecting clips and positioning the cursor" on page 98](#).
2. Click the Clip button  below the timeline and choose Create nested timeline from the menu. The selected clip starts at the 00:00:00;00 position in the new nested timeline.

You can edit the new nested timeline as you would any other project, adding tracks and clips as needed.

When you need to return to the parent timeline, use the breadcrumb trail at the top-left corner of the timeline.



If clips contain automation envelopes before you create a nested timeline, the clip automation envelopes are available in the clips in the nested timeline. The parent clip will use the default single-point envelope. For more information, see ["Clip volume automation" on page 123](#).




You can create a nested timeline from a Catalyst Prepare storyboard () or a Catalyst Browse clip list by adding the storyboard/clip list to the Catalyst Edit timeline.

For more information about using media from a Catalyst Prepare library () , see ["Finding media" on page 27](#).

Opening a nested timeline

1. Select a clip that contains a nested timeline. For more information, see ["Selecting clips and positioning the cursor" on page 98](#).
2. Click the Clip button  below the timeline and choose Open nested timeline from the menu or click the clip icon in the clip header.



The selected timeline is opened.

 The cursor position is maintained when you navigate into or out of a nested timeline.

You can edit the new nested timeline as you would any other project, adding tracks and clips as needed.

When you need to return to the parent timeline, use the breadcrumb trail at the top-left corner of the timeline.

Clip fades


You can use the Fade Tool to control a clip's fade-in, fade-out, and overall level or opacity.

 For more advanced volume control, you can use the Clip Automation Tool. For more information, see ["Clip volume automation" on page 123](#).

Adjusting a clip's volume or opacity

1. Click the Tools button below the timeline and select the Fade Tool  .

 Hold F to switch to the Fade Tool temporarily. When you're finished editing, release the F key, and the previous editing tool will be restored.
2. Hover over the top of the video or audio portion of a clip until the fade cursor is displayed:



3. Drag the line to the desired level. As you drag the line, the clip's gain or opacity is adjusted.

As you decrease the setting, a clip becomes more transparent, allowing clips on lower tracks to show through the clip.

 Adjusting the clip's gain or opacity also adjusts the Gain or Opacity setting in the Clip Inspector. For more information, see ["Using the Clip Inspector" on page 128](#).

Adjusting a clip's fade in or fade out

1. Click the Tools button below the timeline and select the Fade Tool .
 -  Hold F to switch to the Fade Tool temporarily. When you're finished editing, release the F key, and the previous editing tool will be restored.
2. Hover over the left or right edge of a clip until the fade cursor is displayed:



3. Drag the corner of the clip to set the amount of time it takes the clip to fade in or out.

If snapping is enabled, the fade edge will snap to available snap points as you drag it. For more information, see ["Clip snapping" on page 115](#).

If there are no clips on tracks below the selected clip, it will fade from/to black. If a clip is on a track below the selected clip, the lower clip will be visible during the fade.

-  Adjusting the clip's fades also adjusts the Fade in length and Fade out length settings in the Clip Inspector. For more information, see ["Using the Clip Inspector" on page 128](#).

Double-click the fade between two clips with the Edit, Slip, or Fade tool to select a fade area and set the Mark In/Out region to match its length.

Clip volume automation

If you want to adjust a clip's volume over time, you can use an envelope to automate volume over the length of the clip.

-  For simple control over a clip's fade in, fade out, and overall level, you can use the Fade Tool. For more information, see ["Clip fades" on page 122](#).

Clip automation envelopes are independent of clip fades. Using the Fade Tool to adjust the clip's gain or opacity also adjusts the Gain or Opacity setting in the Clip Inspector. For more information, see ["Using the Clip Inspector" on page 128](#).

-  If clips contain automation envelopes before you create a nested timeline, the clip automation envelopes are available in the clips in the nested timeline. The parent clip will use the default single-point envelope. For more information, see "[Nested timelines](#)" on page 119.


Adjusting a clip's volume

1. Click the Tools button below the timeline and select the Envelope Tool .

-  Hold V to switch to the Envelope Tool temporarily. When you're finished editing, release the V key, and the previous editing tool will be restored.

When the Envelope Tool is selected, each clip will display a volume automation envelope.

2. Drag the line to the desired level. As you drag the line, the clip's gain is adjusted.




Drag down to make the clip quieter or drag up to make the clip louder.

If you want to automate volume, add more points to the envelope.

Adding envelope points

To create more complex envelopes, you will need to add points. To add an envelope point, double-click the envelope with the Envelope Tool . A new envelope point will be added.



💡 To add a point, right-click it with the Envelope Tool  and choose Add point.

To delete a point, right-click it with the Envelope Tool  and choose Delete.

To reset an envelope to its default state, right-click an envelope segment or point with the Envelope Tool  and choose Reset all points.

Adjusting an envelope

By default, a new envelope will contain a single envelope point. If you want to adjust the overall level of an envelope, drag the envelope up or down with the Envelope Tool .

If an envelope has multiple points, you can drag each point, or you can drag envelope segments:

- Dragging up or down decreases or increases volume.
- Dragging left or right changes when the volume adjustment occurs.

 You cannot drag an envelope point past another point on the timeline.






As you adjust the envelope, the clip's waveform is updated to reflect the new volume.

💡 Right-click an envelope point with the Envelope Tool  to display a shortcut menu where you can set the selected point to the maximum value (+12 dB), the default (0 dB), or the minimum value (-Inf dB).

To reset an individual point to 0 dB, double-click it with the Envelope Tool .

Setting fade curves

You can adjust the fade curve for each envelope segment individually. To change the fade curve, right-click an envelope segment and choose a command from the shortcut menu.

Fade Type	Fade In/Out Curve
Hold	
Linear	
Fast	
Slow	
Smooth	
Sharp	

Flipping an envelope

Right-click an envelope point with the Envelope Tool  and choose Flip to flip its position around the 0 dB baseline.

Right-click an envelope segment with the Envelope Tool  and choose Flip all to flip an envelope around the 0 dB baseline.

For example, if an envelope point sets the volume to 3 dB, that point will set the volume to -3 dB after flipping the envelope. Values that are less than -12 dB will be 12 dB after flipping the envelope.

Replacing a clip's media

Replacing a clip's media preserves the length and position of a clip on the timeline, but replaces the media file that is displayed by the clip.

For information about relinking a project's media clips, please see ["Relinking project media" on page 13](#).

1. In the timeline, select the clip you want to edit. For more information, see ["Selecting clips and positioning the cursor" on page 98](#).
2. In the Media Browser, select the media file that you want to use to replace the selected clip.
3. Click the Tools button  at the bottom of the Media Browser below the timeline and choose Replace media with selection from the menu.

The clip and is updated to use the file from the Media Browser.

 If you replace a clip with a shorter media file, the last frame of the new file will repeat until the end of the clip.

If you replace a clip with a longer media file, the clip length does not change.

You can trim the clip to match the length of the new media file. For more information, see ["Trimming clips" on page 102](#).

Undoing and redoing edit operations

Undo and Redo give you the freedom to experiment with your project.

Undoing the last action performed

Click the Tools button  below the timeline and choose Undo or press Ctrl+Z (Windows) or ⌘ +Z (macOS).

Reversing the last Undo performed

Click the Tools button  below the timeline and choose Redo or press Ctrl+Shift+Z (Windows) or ⌘ +Shift+Z (macOS).

Using the Clip Inspector

In the Inspector , select the Clip tab to view and edit settings for the selected clip.

 Click a clip to select it, and the Clip tab is displayed automatically if the Inspector is visible.

Summary

Item	Description
Name	Type a value in the Name box to set the name of the selected clip. The name you type here will be displayed in the clip: 
Media	Displays the source file name for the selected clip.

When a clip from a Catalyst Prepare library () is selected, you can click the

Item	Description
	<p data-bbox="472 289 1349 369">Refresh button  to update the clip's properties from the Catalyst Prepare library.</p> <p data-bbox="472 394 1321 485"> You can also click the Clip button  below the timeline and choose Refresh from the menu.</p>
Folder	<p data-bbox="472 527 1198 554">Displays the name of the folder where the source clip is stored.</p> <p data-bbox="472 583 1321 617">Click the folder name to open the location in Windows Explorer or Finder.</p>
Library	<p data-bbox="472 642 1360 737">When a clip from a Catalyst Prepare library () is selected, the Library box displays the name of the clip's source library.</p> <p data-bbox="472 766 1398 898">Click the name of the library to open it in Catalyst Prepare and select the clip. If you perform color correction in Catalyst Prepare, click the Refresh button  to update the clip.</p> <p data-bbox="472 928 1393 1062"> You can also click the Clip button  below the timeline and choose Open <i>library.cpreplib</i> from the menu to open it in Catalyst Prepare and select the clip. .</p>
Streams	<p data-bbox="472 1094 1382 1163">When a clip with audio and video streams is selected, you can click a button to indicate which streams should be included in the timeline.</p> <ul data-bbox="521 1199 1406 1436" style="list-style-type: none"> <li data-bbox="521 1199 1406 1268">▪ Click Audio to include only the audio stream. The video thumbnails will be hidden in the clip and excluded when you render your project. <li data-bbox="521 1297 1406 1367">▪ Click Video to include only the video stream. The audio waveform will be hidden in the clip and excluded when you render your project. <li data-bbox="521 1396 1247 1436">▪ Click Both to include the audio and video streams in the clip. <p data-bbox="472 1465 1382 1535"> The Streams controls are not displayed when an audio-only or video-only clip is selected.</p> <p data-bbox="529 1570 1333 1640">When a track contains a single clip, the track header controls will also change to reflect the current Streams setting.</p>

Editing

Item	Description
Start	<p>Click the value and type a new value to trim the beginning of the selected clip to the specified timeline position.</p> <p>For example, if the current Start value is 0.00, typing 10.00 will move the beginning of the clip ten seconds later on the timeline.</p> <p>If ripple mode is enabled, all subsequent clips will ripple automatically. For more information, see "Ripple edits" on page 114.</p>
End	<p>Click the value and type a new value to trim the end of the selected clip to the specified timeline position.</p> <p>For example, if the current End value is 60.00, typing 50.00 will move the end of the clip ten seconds earlier on the timeline.</p> <p>If ripple mode is enabled, all subsequent clips will ripple automatically.</p>
Length	<p>Click the value and type a new value to set the length of the selected clip. The clip's start point remains fixed on the timeline, and the clip's end is modified as needed.</p> <p>If ripple mode is enabled, all subsequent clips will ripple automatically.</p> <p> If you set a clip's length to zero, the clip is deleted from the timeline.</p>
Source offset	<p>Click the value and type a new value to set the start time of the selected clip. Adjusting the clip's source offset slips the clip's media within the clip: use a negative offset to slip the media to the left or use a positive offset to slip the media to the right.</p> <p>For more information, see "Clip editing" on page 108.</p>
Fade in length	<p>If a clip is not crossfaded with the previous clip, click the value and type a new value to set the amount of time it takes the clip to fade in. If there are no clips on tracks below the selected clip, it will fade in from black. If a clip is on a track below the selected clip, the lower clip will be visible during the fade.</p> <p>Editing this setting also affects the fade envelope on the clip. For more information, see "Clip fades" on page 122.</p>
Fade out length	<p>If a clip is not crossfaded with the previous clip, click the value and type a new value to set the amount of time it takes the clip to fade out. If there are no clips on tracks below the selected clip, it will fade out to black. If a clip is on a track below</p>

Item	Description
	<p>the selected clip, the lower clip will be visible during the fade.</p> <p>Editing this setting also affects the fade envelope on the clip. For more information, see "Clip fades" on page 122.</p>
Opacity	<p>Click the value and type a new value or drag the slider to set the opacity of a clip. Double-click the center of the thumb to reset the slider.</p> <p>Using a setting of 1.0, a clip is completely opaque; clips on lower tracks are not visible. As you decrease the setting, a clip becomes more transparent, allowing clips on lower tracks to show through the clip.</p> <p>Editing this setting also affects the fade envelope on the clip. For more information, see "Clip fades" on page 122.</p>
Rate	<p>Click the value and type a new value or drag the slider to set the playback rate of a clip. Double-click the center of the thumb to reset the slider.</p> <p>A setting of 1 will play at normal speed, while 0.5 will play at half speed. A setting of 0 will create a freeze-frame effect using the first visible frame of the clip.</p> <p>Each video clip in your project has a specific duration that is not changed by adjusting the playback rate. If you decrease the speed of a ten-second video event to .5, only five seconds of video will be shown. On the other hand, if the speed is increased to 2, the ten seconds of video will play in only five seconds. The remaining five seconds of the clip will be filled either with a freeze of the last frame or with ten additional seconds of video content from the media file (if the source media is longer than the clip).</p>
Audio mode	<p>Choose a setting from the drop-down list to choose how audio is stretched when you adjust the playback rate of a clip.</p> <ul style="list-style-type: none"> ▪ None: to time stretching or pitch shifting is applied. ▪ Time stretch: audio is time-stretched to match the clip's rate, but the playback pitch is preserved. ▪ Pitch shift: audio is time-stretched to match the clip's rate, and the playback pitch is raised or lowered to match the rate (faster playback raises the pitch; slower playback lowers the pitch).
Gain	<p>Click the value and type a new value or drag the fader to adjust the volume of each audio channel in the selected clip. Double-click the center of the thumb to reset the fader.</p> <p>Editing this setting also affects the fade envelope on the clip. For more</p>

Item	Description
	information, see "Clip fades" on page 122 .
	When adjusting volume, remember to watch your audio meters. Because you are adding the volumes of all of the tracks together, it is easy to clip the audio output. Make sure that the meters never display the red Clip indication during playback. For more information, see "Monitoring audio levels" on page 167 .

Channel Assignment

Click the speaker icon to turn a channel on  or off .

 Turning off a clip's unused channels allows you to remove those channels from the track list in the timeline.

Click the Mono or Stereo button to indicate whether a channel is a mono channel or part of a stereo pair. Enabling Stereo will pair the channel with the next channel in the list.

 If you want to set all of a clip's channels at once, click the Channel Tools button  and choose Set all to mono, Set all to stereo, or Reset.

Type a name in the edit box to identify the channel. For example, you might type Lav1 to identify audio from a lavalier microphone.

 Channels that are named identically in the Timeline Inspector and Clip Inspector will be matched.

When you add a clip from a Catalyst Prepare library () to the Catalyst Edit timeline, any channel assignment settings that you made in the Catalyst Prepare library will be applied to the clip.

Title

When a title clip is selected, you can use the Title controls to control the appearance of your title text. For more information, see ["Applying effects" on page 141](#).

Video Effects

When the selected clip has effects applied to it, you can use the Video Effects controls to control the settings for each effect. For more information, see ["Adding effects to a clip" on page 135](#).

Click the Overlay button  to show or hide a plug-in's interactive overlay controls in the video preview (when available).


Click the Mute button  to bypass a plug-in without removing it from the chain.

Click the Delete button  to remove a plug-in from the chain.

Drag a plug-in's heading to change its position in the plug-in chain.

Click the toggle arrow to show or hide each plug-in's controls.

When you select a position parameter in the Inspector, a control point () is displayed in the video preview. You can adjust the parameter's position by dragging the control point in the video preview or the Inspector:



Applying effects

You can use effects to manipulate the video components of your project.

The included video plug-ins include effects, transitions, and text/background generators. Effects can be used to improve video quality or manipulate an image, transitions can change the way video events flow into one another, and generators can create text and backgrounds.

Using video effects

There are several methods available for applying effects to video. Video effects can be applied to clips, tracks, or to the entire video timeline.


 You can use split-screen previews to preview your project with and without video effects. For more information, see ["Previewing video" on page 65](#).

Adding effects to a clip

Effects that you apply to a clip are applied only to that clip.

1. Click the Plug-Ins button  at the top of the Catalyst Edit window to display the Plug-Ins pane and select the effect you want to use.
2. On the timeline, select the clip where you want to apply the effect. For more information, see ["Selecting clips and positioning the cursor" on page 98](#).
3. Click the Add to Clip button  at the bottom of the Plug-Ins pane or drag the effect to the clip.

An effects indicator is displayed on a clip when it has effects applied. You can click the indicator to display the effect's controls in the Clip Inspector.



4. Use the controls in the Clip Inspector to adjust the effect's settings.

For more information, see ["Using the Clip Inspector" on page 128](#).

Click the Overlay button  to show or hide a plug-in's interactive overlay controls in the video preview (when available).

Click the Mute button  to bypass a plug-in without removing it from the chain.

Click the Delete button  to remove a plug-in from the chain.

Drag a plug-in's heading to change its position in the plug-in chain.

Click the toggle arrow to show or hide each plug-in's controls.

When you select a position parameter in the Inspector, a control point () is displayed in the video preview. You can adjust the parameter's position by dragging the control point in the video preview or the Inspector:




Adding effects to a track

Effects that you apply to a track are applied to every clip on that track.

1. Click the Plug-Ins button  at the top of the Catalyst Edit window to display the Plug-Ins pane and select the effect you want to use.
2. Click a track's header to select the track where you want to apply the effect.
3. Click the Add to Track button  at the bottom of the Plug-Ins pane or drag the effect to the track header.

An effects indicator is displayed on a track when it has effects applied. You can click the indicator to display the effect's controls in the Track Inspector.



4. Use the controls in the Track Inspector to adjust the effect's settings.

For more information, see ["Using the Track Inspector" on page 86](#).

Click the Overlay button  to show or hide a plug-in's interactive overlay controls in the video preview (when available).

Click the Mute button  to bypass a plug-in without removing it from the chain.

Click the Delete button  to remove a plug-in from the chain.

Drag a plug-in's heading to change its position in the plug-in chain.

Click the toggle arrow to show or hide each plug-in's controls.


When you select a position parameter in the Inspector, a control point () is displayed in the video preview. You can adjust the parameter's position by dragging the control point in the video preview or the Inspector:



Adding effects to the timeline

Effects that you apply to the timeline are a clip are applied only to that clip.

1. Click the Plug-Ins button  at the top of the Catalyst Edit window to display the Plug-Ins pane and select the effect you want to use.
2. Click the Add to Timeline button  at the bottom of the Plug-Ins pane or drag the effect to the timeline breadcrumb trail above the track list.



3. Use the controls in the Timeline Inspector to adjust the effect's settings.

For more information, see ["Using the Timeline Inspector" on page 14](#).

 Click the Overlay button  to show or hide a plug-in's interactive overlay controls in the video preview (when available).

Click the Mute button  to bypass a plug-in without removing it from the chain.

Click the Delete button  to remove a plug-in from the chain.

Drag a plug-in's heading to change its position in the plug-in chain.

Click the toggle arrow to show or hide each plug-in's controls.

When you select a position parameter in the Inspector, a control point () is displayed in the video preview. You can adjust the parameter's position by dragging the control point in the video preview or the Inspector:



Using video generators

You can use video generators to create backgrounds, text, and textures in your project.

1. Click to select a track.
2. Click the Plug-Ins button  at the top of the Catalyst Edit window to display the Plug-Ins pane.
3. Expand the Video Generators heading.
4. Click a video generator to select it.
5. Click the Add Generator button . The selected generator is added as a clip to the end of the selected track, and the new clip is selected.

 You can also drag a generator plug-in from the Plug-Ins pane to the timeline to create a clip.

You can also use the Add button below the timeline to quickly add the Title, Solid Color, or Color Gradient plug-in to the selected track. For more information, see ["Applying effects" on page 141](#), ["Applying effects" on page 146](#), or ["Applying effects" on page 147](#).

6. Use the controls in the Clip Inspector to adjust the generator's settings.

For more information, see ["Using the Clip Inspector" on page 128](#).

Adding title clips

You can add title clips to your project to create titles and credits.

Adding a title clip

1. Click to select a track.
2. Click to position the cursor where you want to add the title clip.
3. Click the Add button  below the timeline and choose Title. The clip is created at the cursor position on the timeline.

 You can also drag the Title generator from the Plug-Ins pane to the timeline to create a title clip.

4. Use the controls in the Clip Inspector to adjust the generator's settings.

Editing a title clip

1. Select the clip you want to edit.
2. Click the Inspector button to show the Inspector pane.
3. In the Inspector, select the Clip tab to view and edit settings for the selected title clip.

For more information, see ["Using the Clip Inspector" on page 128](#).


Item	Description
Text	Type in the edit box to set the text that will be displayed by your clip.
Position	<p>The drop-down list displays the current position of the text in the frame. Click to display an edit control you can use to position your text.</p>  <p>You can drag the point in the edit control or type values in the X and Y boxes to set the position of your text in the frame. Double-click the point to reset it.</p> <p> Hold Ctrl (Windows) or ⌘ (macOS) to adjust the point in fine increments.</p>
Size	<p>Type a value in the box or drag the slider to adjust the size of the text.</p> <p> Hold Ctrl (Windows) or ⌘ (macOS) to adjust the slider in fine increments.</p> <p>You can drag the slider past the end of the trackbar to unlock the full range of the control. When the value is set outside the range of the slider, the handle will be displayed as  or .</p>
Font	Choose a font from the drop-down list to set the typeface that will be used for your text.
Bold	Click to toggle boldface text for the selected clip.
Italic	Click to toggle italicized text for the selected clip.

Item	Description
Color	Click the color sample to display a color picker, where you can choose a color or type color values to set the text color. You can also adjust the transparency (alpha value) of the text.
Rotation	Type a value in the box or drag the slider to adjust the angle of the text in the frame.
Alignment	
Horizontal	<p>Choose a setting from the drop-down list to indicate how your text is aligned within the text box and how the text box is aligned with the point specified by the Position value:</p> <ul style="list-style-type: none"> ▪ Select Left to left justify the text in the box and align the left edge of the text box with the Position point. ▪ Select Center to center justify the text in the box and align the center of the text box with the Position point. ▪ Select Right to right justify the text in the box and align the right edge of the text box with the Position point.
Vertical	<p>Choose a setting from the drop-down list to indicate how your text box is aligned with the point specified by the Position value:</p> <ul style="list-style-type: none"> ▪ Select Top to align the top of the text box with the Position point. ▪ Select Center to align the center of the text box with the Position point. ▪ Select Baseline when you have a single line of text and want to align the text's baseline with the Position point. ▪ Select Bottom to align the bottom of the text box with the Position point.
Background	
Color	<p>Click the color sample to display a color picker, where you can choose a color or type color values to adjust the background. You can also adjust the transparency (alpha value) of the background.</p> <p>Adding a background color makes it easy to create a lower-third color box.</p>
Location	The drop-down list displays the current position of the text background in the frame. Click to display an edit control you can use to set the position

Item

Description

of each corner of the background in the frame.



Adjusting box position

Drag the point in the edit control to set the position of the background in the frame. Double-click the point to reset it.

When you type values in the Dimensions tab, you can set an anchor point and specify the position of the box using X/Y coordinates. For example, click the top-right corner of the anchor control and use the coordinates 0.5000, 0.5000 to move the top-right corner of the box to the center of the control.

Adjusting box dimensions

You can drag the corners of the rectangle in the edit control or type values in the W and H edit boxes to set the size of the frame.

When you type values in the Dimensions tab, you can set the size of the box using W/H dimensions. Click the Lock button  to preserve the aspect ratio of the box so changing the width or height will automatically update the other value,

Adjusting box edges

You can drag the edges of the rectangle in the edit control or type values in the Edges tab to specify the position for each edge of the box.

Item	Description
	<p data-bbox="581 281 1325 352"> Drag a corner of the rectangle to preserve aspect ratio while resizing.</p> <p data-bbox="630 386 1403 457">Hold Shift while dragging the corners of the rectangle to resize and adjust aspect ratio.</p> <p data-bbox="630 491 1403 562">Hold Alt (Windows) or Option (macOS) to resize the rectangle from the center.</p> <p data-bbox="630 596 1364 667">Hold Ctrl (Windows) or ⌘ (macOS) to adjust the controls in fine increments.</p> <p data-bbox="630 701 1412 810">When a corner is selected, you can use the arrow keys to adjust the selected corner, or press Ctrl (Windows) or ⌘ (macOS) + the arrow keys to adjust in fine increments.</p> <p data-bbox="573 848 1211 877">Drag the edges of the rectangle to resize the rectangle.</p>
	<p data-bbox="581 911 1325 982"> Drag an edge of the rectangle to preserve aspect ratio while resizing.</p> <p data-bbox="630 1016 1403 1045">Hold Shift while dragging an edge to resize and adjust aspect ratio.</p> <p data-bbox="630 1079 1403 1150">Hold Alt (Windows) or Option (macOS) to resize the rectangle from the center.</p> <p data-bbox="630 1184 1364 1255">Hold Ctrl (Windows) or ⌘ (macOS) to adjust the controls in fine increments.</p>
	<p data-bbox="573 1289 1412 1360">Drag the center of the rectangle to move without resizing, or double-click the point to reset it.</p>
	<p data-bbox="581 1394 1351 1465"> Hold Shift while dragging to constrain to horizontal/vertical/45-degree movement.</p> <p data-bbox="630 1499 1364 1570">Hold Ctrl (Windows) or ⌘ (macOS) to adjust the controls in fine increments.</p> <p data-bbox="630 1604 1370 1675">When the rectangle is selected, you can copy the position of the rectangle to paste to another clip.</p>
Shadow	
Enable	Click to toggle a shadow behind your text.
Color	Click the color sample to display a color picker, where you can choose a

Item	Description
	color or type color values to set the shadow color. You can also adjust the transparency (alpha value) of the shadow.
Feather	Type a value in the box or drag the slider to blend the shadow with the background.  Hold Ctrl (Windows) or ⌘ (macOS) to adjust the slider in fine increments.
Offset X/Y	Type a value in the box or drag the slider to offset the shadow from the center of your text.  Hold Ctrl (Windows) or ⌘ (macOS) to adjust the slider in fine increments.
Outline	
Enable	Click to toggle an outline around your text.
Color	Click the color sample to display a color picker, where you can choose a color or type color values to set the outline color. You can also adjust the transparency (alpha value) of the outline.
Thickness	Type a value in the box or drag the slider to adjust the thickness of the text outline.  Hold Ctrl (Windows) or ⌘ (macOS) to adjust the slider in fine increments.

Adding solid-color clips

You can add solid-color clips to your project to provide backgrounds behind overlays or graphics with transparency or for fades.

Adding a solid-color clip

1. Click to select a track.
2. Click the Add button  below the timeline and choose Solid Color. The clip is created on the timeline.

 You can also drag the Solid Color generator from the Plug-Ins pane to the timeline to create a title clip.
3. Use the controls in the Clip Inspector to adjust the generator's settings.

Editing a solid-color clip

1. Select the title clip you want to edit.
2. Click the Inspector button to show the Inspector pane.
3. In the Inspector, select the Clip tab to view and click the color sample to display a color picker, where you can choose a color or type color values to set the text color. You can also adjust the transparency (alpha value) of the color.

For more information, see ["Using the Clip Inspector" on page 128](#).

Adding color-gradient clips

You can add color-gradient clips to your project to provide an interesting variety of backgrounds behind overlays or graphics with transparency or for fades.

Adding a color-gradient clip

1. Click to select a track.
2. Click the Add button  below the timeline and choose Color Gradient. The clip is created on the timeline.



You can also drag the Color Gradient generator from the Plug-Ins pane to the timeline to create a title clip.



3. Use the controls in the Clip Inspector to adjust the generator's settings.

Editing a color-gradient clip

1. Select the title clip you want to edit.
2. Click the Inspector button to show the Inspector pane.
3. In the Inspector, select the Clip tab to view and edit settings for the selected title clip.

For more information, see ["Using the Clip Inspector" on page 128](#).

Item	Description
Type	Choose a setting from the drop-down list to choose the shape of the gradient.
Center	The drop-down list displays the current position of the gradient in the

Item	Description
	<p>frame. Click to display an edit control you can use to position the gradient.</p>  <p>You can drag the point in the edit control or type values in the X and Y boxes to set the position of your gradient in the frame. Double-click the point to reset it.</p> <p> Hold Ctrl (Windows) or ⌘ (macOS) to adjust the point in fine increments.</p>
Angle	Type a value in the box or drag the slider to adjust the angle of the line formed by the control points in relation to a horizontal plane.
Control Point	
Distance	Type a value in the box or drag the slider to adjust the distance of the control point from the center.
Location	<p>The drop-down list displays the current position of the control point in the frame. Click to display an edit control you can use to position the point.</p>  <p>You can drag the point in the edit control or type values in the X and Y boxes to set the position of your control point in the frame. Double-click the point to reset it.</p> <p> Hold Ctrl (Windows) or ⌘ (macOS) to adjust the point in fine increments.</p>
Color	Click the color sample to display a color picker, where you can choose the color you want to display at the selected control point.
Remove	Removes the selected control point.
Add	Adds a new gradient control point.

Using video transitions

You can use video transitions to control how a video event begins or ends, or to change the way one event flows into another.

1. Select the clip where you want to add a transition.
2. Click the Plug-Ins button  at the top of the Catalyst Edit window to display the Plug-Ins pane.
3. Expand the Video Transitions heading.
4. Click a transition to select it.
5. Click the Set Transition In  or Set Transition Out  button to add the selected transition to the beginning or end of the selected clip.

When two clips overlap, add the transition to the beginning of the second clip to set the transition for the overlapping area.

 You can also drag a transition from the Plug-Ins pane to the overlapping area between two clips.



6. Use the Fade Tool to adjust the transition length. For more information, see ["Clip fades" on page 122](#).
7. Use the controls in the Clip Inspector to adjust the transition's settings.

For more information, see ["Using the Clip Inspector" on page 128](#).

 Click the Mute button  to bypass a plug-in.

Click the Delete button  to remove a plug-in.

Creating a picture-in-picture effect

The Picture in Picture effect allows you to resize and position clips for picture-in-picture compositing.

Creating the inner picture

1. Create two tracks in your project. For more information, see ["Adding tracks to a project" on page 75](#).
2. Add clips to your tracks:
 - The top track will contain the smaller, inner picture.
 - The bottom track will contain the background clip.

For more information, see ["Adding media and creating clips" on page 60](#).

3. Click the top track to select it.
4. Click the Track button  below the timeline and choose Picture in Picture. The controls for the Picture in Picture plug-in are displayed in the Track Inspector.


Editing picture in picture settings

1. Select the track that contains the top clip.
2. Click the Inspector button to show the Inspector pane.
3. In the Inspector, select the Track tab to view and edit settings for the Picture in Picture plug-in. Use the Picture in Picture plug-in to adjust the size and position of the top clip.

For more information, see ["Using the Track Inspector" on page 86](#).

Item	Description
Location	The drop-down list displays the current position of the video in the frame. Click to display an edit control you can use to position your video.

Item	Description
------	-------------



Adjusting box position

Drag the point in the edit control to set the position of your video in the frame. Double-click the point to reset it.

When you type values in the Dimensions tab, you can set an anchor point and specify the position of the box using X/Y coordinates. For example, click the top-right corner of the anchor control and use the coordinates 0.5000, 0.5000 to move the top-right corner of the box to the center of the control.

Adjusting box dimensions


You can drag the corners of the rectangle in the edit control or type values in the W and H edit boxes to set the size of the frame.

When you type values in the Dimensions tab, you can set the size of the box using W/H dimensions. Click the Lock button  to preserve the aspect ratio of the box so changing the width or height will automatically update the other value,

Adjusting box edges

You can drag the edges of the rectangle in the edit control or type values in the Edges tab to specify the position for each edge of the box.

Item	Description
	<p data-bbox="526 275 1268 348"> Drag a corner of the rectangle to preserve aspect ratio while resizing.</p> <p data-bbox="574 384 1295 457">Hold Shift while dragging the corners of the rectangle to resize and adjust aspect ratio.</p> <p data-bbox="574 489 1289 562">Hold Alt (Windows) or Option (macOS) to resize the rectangle from the center.</p> <p data-bbox="574 594 1308 667">Hold Ctrl (Windows) or ⌘ (macOS) to adjust the controls in fine increments.</p> <p data-bbox="574 699 1312 810">When a corner is selected, you can use the arrow keys to adjust the selected corner, or press Ctrl (Windows) or ⌘ (macOS) + the arrow keys to adjust in fine increments.</p> <p data-bbox="521 846 1154 877">Drag the edges of the rectangle to resize the rectangle.</p> <p data-bbox="526 909 1268 982"> Drag an edge of the rectangle to preserve aspect ratio while resizing.</p> <p data-bbox="574 1014 1284 1087">Hold Shift while dragging an edge to resize and adjust aspect ratio.</p> <p data-bbox="574 1119 1289 1192">Hold Alt (Windows) or Option (macOS) to resize the rectangle from the center.</p> <p data-bbox="574 1224 1308 1297">Hold Ctrl (Windows) or ⌘ (macOS) to adjust the controls in fine increments.</p> <p data-bbox="521 1329 1305 1402">Drag the center of the rectangle to move without resizing, or double-click the point to reset it.</p> <p data-bbox="526 1434 1295 1507"> Hold Shift while dragging to constrain to horizontal/vertical/45-degree movement.</p> <p data-bbox="574 1539 1308 1612">Hold Ctrl (Windows) or ⌘ (macOS) to adjust the controls in fine increments.</p> <p data-bbox="574 1644 1312 1717">When the rectangle is selected, you can copy the position of the rectangle to paste to another clip.</p>
Rotation	Type a value in the box or drag the slider to rotate the video in the frame.

Item	Description
Flip horizontal	Click to invert the video horizontally.
Flip vertical	Click to invert the video vertically.
Opacity	Type a value in the box or drag the slider to adjust the opacity of the top image. As you decrease the opacity, video from lower tracks will show through the foreground.
Shadow	
Type	Choose a setting from the drop-down list if you want to display a shadow over or behind the foreground image.
Offset	The drop-down list displays the current position of the shadow relative to the foreground image. Click to display an edit control you can use to position your shadow.
	
	<p>You can drag the point in the edit control or type values in the X and Y boxes to set the position of your shadow in the frame. Double-click the point to reset it.</p> <p> Hold Ctrl (Windows) or ⌘ (macOS) to adjust the point in fine increments.</p>
Rotation	Type a value in the box or drag the slider to rotate the shadow in the frame.
Scale	Type a value in the box or drag the slider to adjust the size of the shadow.
Blur	Type a value in the box or drag the slider to feather the edges of the shadow.
Opacity	Type a value in the box or drag the slider to adjust the opacity of the shadow. As you decrease the opacity, video from lower tracks will show through the foreground.
Glow	
Type	Choose a setting from the drop-down list if you want to display a glow effect over or behind the foreground image.

Item	Description
Amount	Type a value in the box or drag the slider to adjust the size of the glow effect.
Color/Second color	Click the color sample to display a color picker, where you can choose a color or type color values to set the shadow color. You can also adjust the transparency (alpha value) of the shadow.

Animating video parameters with keyframes

Keyframes define the state of an effect's parameters for a specified point on the timeline. The settings for intermediate frames are interpolated to create smooth animation.


You can click the Keyframe Editor button  at the bottom of the Inspector to switch the timeline to keyframe mode, where you can edit parameters for individual keyframes.

Adding keyframes

In the Inspector window, each parameter that can be automated displays a Keyframes button . Select the button to create a row in the keyframe editor for that parameter.

1. Add an effect to your project. For more information, see ["Using video effects" on page 135](#).
2. Select the track or clip where you added the effect and click the Timeline Inspector, Track Inspector, or Clip Inspector.
3. Select the effect in the Timeline Inspector, Track Inspector, or Clip Inspector.
4. In the Inspector, select the Keyframes button  for the parameter you want to animate. An initial keyframe is created, and the timeline switches to keyframe mode.


Notice that the keyframe editor includes a row for each keyframed parameter



5. In the keyframe editor, click to position the cursor where you want to add a keyframe  You can also double-click the keyframe editor to add a keyframe or click the Add button  in the toolbar below the keyframe editor.
6. In the Inspector, adjust the parameter's control as needed. A keyframe is added to the keyframe editor.
7. Click the Keyframe Editor button  at the bottom of the Inspector to exit keyframe mode when you're finished editing.

Editing keyframes

1. Click a keyframe to select it. The keyframe's current value is displayed in the keyframe editor.



 Click the Previous  or Next  button in the toolbar below the keyframe editor.

2. In the Inspector, adjust the parameter's control as needed. The selected keyframe is updated.

Moving keyframes

You can drag a keyframe in the keyframe editor to change its position on the timeline.

Removing keyframes

Select a keyframe in the keyframe editor and press Delete to remove it from the timeline or click the Remove button  in the toolbar below the keyframe editor.

Chapter 8

Working with audio

Catalyst Edit provides a flexible audio workflow. You can create mono, stereo, or multichannel projects and use each track's audio controls to adjust your mix precisely.

Audio volume and panning

Catalyst Edit allows you to adjust the audio mix of your project by controlling the overall volume of the project, adjusting volume and panning for each track, and adjusting volume for each clip.

Adjusting your project volume

The Gain fader in the Timeline Inspector controls the overall volume of your project.


As you drag the fader, the meters in the Timeline Inspector and in the activity pane at the top of the Catalyst Edit window are updated.

For more information, see ["Using the Timeline Inspector" on page 14](#) and ["Monitoring audio levels" on page 167](#).

Adjusting track volume and panning

Each track provides controls to adjust the volume that is sent to the project's main output.

The Volume fader in the track header controls the volume of the track, and the Pan knob adjusts the position of the track in the stereo field.



The Track Inspector also provides access to the track Volume fader and Pan knob and allows you to change the panning model that is used for the track.

As you drag the fader and knob, the meters in the Track Inspector display the levels for the current track, and the meters in the activity pane at the top of the Catalyst Edit window display the overall project levels.

For more information, see ["Adjusting track controls" on page 82](#), ["Using the Track Inspector" on page 86](#), and ["Monitoring audio levels" on page 167](#).

Adjusting clip volume

Each clip provides controls to adjust the volume that is sent to the track.

You can use the Fade Tool to adjust the clip's gain:



The Clip Inspector also provides access to the clip level via the Gain fader.

For more information, see ["Clip fades" on page 122](#), ["Using the Clip Inspector" on page 128](#), and ["Monitoring audio levels" on page 167](#).

Working with multichannel audio

Catalyst Edit makes it easy to use your camera audio and incorporate audio from other sources into your project.

- The Audio and Channel Output controls in the Timeline Inspector allow you to specify the number of audio channels for your project.
- The Audio controls in the Track Inspector allow you to adjust levels and panning for each channel.
- The Channel Assignment controls in the Clip Inspector allow you to configure how the clip's audio channels feed the track's audio channels.

Setting up the project timeline audio channels

1. Click the Inspector button  to show the Inspector window (if it isn't already visible) and click the Timeline tab.
2. Choose a setting from the Channel setup from the drop-down list to choose whether you're creating a mono, stereo, or multichannel project.

If you choose Multichannel, type a number in the Channel count box to set the number of channels to create a multichannel project.

3. Use the Channel Output controls to set up the timeline's channels.
 - a. Click the speaker icon to turn a channel on  or off .

 Turning a channel off mutes it during playback and rendering. For example, if you were preparing an eight-channel project with English dialog on channels 1 & 2, French dialog on channels 3 & 4, Spanish dialog on channels 5 & 6, and music on channels 7 & 8, you could turn off dialog channels to preview your project and then turn the channels on when you render your final eight-channel file for delivery. For more information, see ["Rendering projects" on page 20](#).

- b. Click the Mono/Stereo button to indicate whether a channel is a mono channel or part of a stereo pair. Enabling Stereo will pair the channel with the next channel in the list.
- c. Type a name in the edit box to identify the channel. For example, you might type Lav1 to identify audio from a lavalier microphone.

 Channels that are named identically in the Timeline Inspector and Clip Inspector will be matched.

When you add a clip from a Catalyst Prepare library () to the Catalyst Edit timeline, any channel assignment settings that you made in the Catalyst Prepare library will be applied to the clip.


For more information, see ["Using the Timeline Inspector" on page 14](#).

Setting up a track's audio channels

1. Click a track header to select the track you want to edit.
2. The track header and the Track Inspector provide controls you can use to mix the track for your project's output.

For more information, see ["Adjusting track controls" on page 82](#) and ["Using the Track Inspector" on page 86](#).

- If the Timeline Inspector is set for a mono project, each track will display a blue Volume fader you can use to adjust the overall level of the track and Mute and Solo buttons you can use to mute or solo the track.




Additionally, if the track contains clips that have multiple channels assigned on the Clip Inspector, each channel provides an orange Volume fader you can use to adjust the channel's contribution to the level of the track and Mute and Solo buttons you can use to mute or solo the channel.




- If the Timeline Inspector is set for a stereo project, each track will display a blue Volume fader you can use to adjust the overall level of the track and Mute and Solo buttons you can use to mute or solo the track.

If the timeline outputs are stereo, each track provides a Pan control that you can use to pan the track to the timeline outputs. If the timeline outputs are mono, each track provides an Output control that you can use to assign the track to the timeline outputs.




Additionally, if the track contains clips that have multiple channels assigned on the Clip Inspector, each channel provides an orange Volume fader you can use to adjust the channel's contribution to the level of the track and Mute and Solo buttons you can use to mute or solo the channel.

If the timeline outputs are stereo, each channel provides an orange Pan control that you can use to pan the channel to the timeline outputs. If the timeline outputs are mono, each channel provides an Output control that you can use to assign the channel to the timeline outputs.




- If the Timeline Inspector is set for a multichannel project, each track will display a blue Volume fader you can use to adjust the overall level of the track, Mute and Solo buttons you can use to mute or solo the track, and an Output control that you can use to assign the track to the timeline outputs.

If the timeline outputs are stereo, each track provides a Pan control that you can use to pan the track to the timeline outputs.



Additionally, if the track contains clips that have multiple channels assigned on the Clip Inspector, each channel provides an orange Volume fader you can use to adjust the channel's contribution to the level of the track, Mute and Solo buttons you can use to mute or solo the channel, and an Output control that you can use to assign the channel to the timeline outputs.

If the timeline outputs are stereo, each channel provides an orange Pan control that you can use to pan the channel to the timeline outputs.



When adjusting volume, remember to watch your audio meters. Because you are adding the volumes of all of the tracks together, it is easy to clip the audio output. Make sure that the meters never display the red Clip indication during playback. For more information, see ["Monitoring audio levels" on page 167](#).

The meters in the Track Inspector show audio levels for the selected track and each of the channels that contributes to the track.


The meter in the activity pane at the top of the Catalyst Edit window shows the sum of all audio at the cursor position.

Assigning a clip's audio channels

1. Select the clip you want to edit. For more information, see ["Selecting clips and positioning the cursor" on page 98](#).

2. Click the Inspector button  to show the Inspector window (if it isn't already visible) and click the Clip tab.
3. Use the controls in the Channel Assignment section to set up the clip's audio:
 - a. Click the speaker icon to turn a channel on  or off .

Each channel will be displayed in a separate lane in the timeline.



Click  to expand the track's channels.

- b. Click the Mono/Stereo button to indicate whether a channel is a mono channel or part of a stereo pair. Enabling Stereo will pair the channel with the next channel in the list.

 Mono channels will not display a Pan control in the track header. For more information, see ["Adjusting track controls" on page 82](#).
 - c. Type a name in the edit box to identify the channel. For example, you might type Lav1 to identify audio from a lavalier microphone.

When multiple clips on a track use the same channel names, those channels will be matched.


The channels that you assign on the Clip tab will be available on the Track tab.

Monitoring audio levels

You can use meters to monitor the audio levels in your project and to ensure that the audio signal is not clipped.

Timeline meter

The meters in the activity pane at the top of the Catalyst Edit window and in the Timeline Inspector display instantaneous levels during playback to help you determine the loudest level in your audio signal and whether the signal is clipping. This peak level represents the sum of all audio at the cursor position.



- During playback, the bars represent the peak audio level at the cursor for each channel.
- The peak level is displayed at the end of the meter.


- If the signal exceeds 0.0 dB, the meters display a red clipping indicator. You can click the clipping indicator to reset it.

💡 The peak level and clipping indicators are reset when you start playback.

Track meter

The meters in the track header and Track Inspector show audio levels for the selected track.

When a track has multiple channels, separate meters are displayed for each channel.



For more information, see ["Adjusting track controls" on page 82](#) and ["Using the Track Inspector" on page 86](#).

Editing Catalyst Edit options

Click the Options  button to edit your application options.

Application settings

Choosing an audio playback device

Choose a setting from the Audio device drop-down list to choose the audio output device that will be used for playback.

Choose Microsoft Mapper (Windows) or System Default (macOS) if you want to use the operating system's default playback device, or choose another compatible audio device from the drop-down list to use a specific device.

 If you switch the audio device during playback, playback will pause and resume automatically.

(Windows only) If a device is not available, it will be listed as offline in the Audio Device drop-down list. After you reconnect the device, choose the device again, and its status will be updated.

Choosing a video processing device

Choose a setting from the Video processing device drop-down list to enable or bypass GPU-accelerated video playback and rendering.

Choose CPU if you want to turn off GPU acceleration, or choose a device from the list to enable GPU-accelerated playback.

 The optimal GPU device is automatically selected. Changing this value is intended for advanced users and may be useful for troubleshooting technical problems.

 Computers equipped with CPUs that utilize Intel's Quick Sync Video (QSV) technology see improved processing performance for decoding H.264/AVC/MPEG-4 video files.

Choosing an external video monitor device and resolution

Choose a setting from the External monitor device drop-down list to display your video preview on an external monitor via a Blackmagic Design device:

- DeckLink 4K Extreme 12G, 4K Pro, 4K Extreme, Studio 4K, SDI 4K, HD Extreme, Extreme 3D, and Mini Monitor.
- Intensity Shuttle, Pro 4K, and Pro.
- UltraStudio 4K Extreme, 4K, Pro, SDI, Express, and Mini Monitor.

Choose a setting from the Monitor resolution drop-down list to choose the display resolution for your monitor.

Configuring video displays

Use the Primary display switch to toggle the video preview above the timeline.

Enable the Secondary window switch if you want to show the video preview in a secondary window that you can position anywhere on your screen or on a secondary monitor.



If you want to use the primary display and secondary window to preview files from the Media Browser, click the Media Browser Settings button  to display the Media Browser Settings menu, and then use the Primary display and Secondary window buttons. For more information, see ["Finding media" on page 27](#).

Customizing keyboard shortcuts

Choose a setting from the Keyboard shortcuts drop-down if you'd like to replace the standard Catalyst Edit shortcut keys with commonly used shortcuts from another editor.

For a listing of the available keyboard shortcuts, please see ["Keyboard shortcuts" on page 171](#).

Chapter 10

Keyboard shortcuts

Shortcut keys can help streamline your work with Catalyst Edit software. The available shortcut keys are arranged in tables according to function.

Global shortcuts

Command	Windows Shortcut	macOS Shortcut
Show/hide the Media Browser	Ctrl+B	⌘ -B
Show/hide the Media Browser	Ctrl+1	⌘ -1 or Control-⌘ -1
 When using Final Cut Pro shortcuts.		
Show/hide the Inspector	Ctrl+I	⌘ -I
Show/hide the Inspector	Ctrl+4	⌘ -4
 When using Final Cut Pro shortcuts.		
Show/hide the secondary window	Alt+V	Option-V
Open application help	F1	Fn-F1 (F1 if the Use all F1, F2, etc. keys as standard function keys setting is selected)

Project file shortcuts

Command	Windows Shortcut	macOS Shortcut
Create project	Ctrl+N	⌘ -N
Open project	Ctrl+O	⌘ -O
Save project	Ctrl+S	⌘ -S
Save project as	Ctrl+Shift+S	Shift-⌘ -S

General editing

Command	Windows Shortcut	macOS Shortcut
Undo	Ctrl+Z	⌘ -Z
Redo	Ctrl+Shift+Z Ctrl+Y	Shift-⌘ -Z

Media Browser

The following keyboard shortcuts are available when the Media Browser pane has focus.

Command	Windows Shortcut	macOS Shortcut
Navigate files/folders	Up, Down, Left, or Right Arrow	Up, Down, Left, or Right Arrow
Open/close folder in tree view	Right/Left Arrow	Right/Left Arrow
Load file and start/pause playback	Spacebar	Spacebar
Open selected folder	Enter or Ctrl+Down Arrow	Return or ⌘ - Down Arrow
Navigate up one level	Backspace	⌘ -Up Arrow
Set mark in point	I	I
Set mark out point	O	O
Go to mark in/out point	Home End	Home or Fn- Left Arrow End or Fn- Right Arrow
Go to mark in point	Shift+I	Shift-I
 When using Final Cut Pro shortcuts.		
Go to mark out point	Shift+O	Shift-O
 When using Final Cut Pro shortcuts.		
Go to start/end of clip	Ctrl+Home Ctrl+End	⌘ -Home ⌘ -End
Go to start/end of clip	Home End	Home or Fn- Left Arrow End or Fn- Right Arrow
 When using Final Cut Pro shortcuts.		
Go to previous/next point (beginning, mark in/out, end)	Ctrl+Left Arrow Ctrl+Right Arrow	⌘ -Left Arrow ⌘ -Right Arrow

Command	Windows Shortcut	macOS Shortcut
Move selection up/down one page	Page Up	Page Up
	Page Down	Page Down

Playback and preview

The following keyboard shortcuts are available when the Video pane has focus.

Command	Windows Shortcut	macOS Shortcut
Go to start	Home	Home Fn- Left Arrow
Go to mark out time (if set) or end of last clip	End	End Fn- Right Arrow
Move one pixel left	Left Arrow	Left Arrow
Move one pixel left  When using Final Cut Pro shortcuts.	Alt+Left Arrow	Option-Left Arrow
Go to previous frame	Alt+Left Arrow	Option-Left Arrow
Go to previous frame  When using Final Cut Pro shortcuts.	Left Arrow	Left Arrow
Move one pixel right	Right Arrow	Right Arrow
Move one pixel right  When using Final Cut Pro shortcuts.	Alt+Right Arrow	Option-Right Arrow
Go to next frame	Alt+Right Arrow	Option-Right Arrow
Go to next frame  When using Final Cut Pro shortcuts.	Right Arrow	Right Arrow
Move to previous/next ruler division	Page Up Page Down	Page Up Page Down
Start/pause playback (when any window has focus)	Ctrl+ Spacebar F12	Option-Spacebar
Start/pause playback (when the timeline has focus)	Spacebar	Spacebar

Command	Windows Shortcut	macOS Shortcut
Start/stop playback (when any window has focus)	Ctrl+ Enter	Option-Return
Start/stop playback	Enter	Return
Shuttle playback	J/K/L	
	Press J or L once for 1x playback.	
	Press J or L twice for 1.5x playback.	
	Press J or L three times for 2x playback.	
	Press J or L four times for 4x playback.	
	Press K to pause playback.	
	Press and hold K while pressing J or L to emulate a shuttle knob mode: press K+J to turn the knob to the left or K+L to turn the knob to the right.	
Toggle looped playback	Q Ctrl+L	Q ⌘ -L
Set Mark In point	I	I
Set Mark Out point	O	O
Switch between Before/After/Split/2 Up video preview.	1/2/3/4	1/2/3/4
Show/hide the secondary window	Alt+V	Option-V

Timeline editing

The following keyboard shortcuts are available when editing clips on the timeline.

Command	Windows Shortcut	macOS Shortcut
Move selected clips left/right	Numeric Keypad 4/6	Numeric Keypad 4/6
Slip trim selected clips one pixel left/right	Alt+Numeric Keypad 4/6	Option-Numeric Keypad 4/6
Switch to the Edit Tool (when timeline or video preview has focus)	E	E

 Hold E to switch to the Edit Tool temporarily. When you're finished editing, release the E key, and the previous editing tool will be restored.

For more information, see ["Editing tools" on page 95](#).

Switch to the Roll Trim Tool (when timeline or video preview has focus)	R	R
---	---	---

 Hold R to switch to the Roll Trim Tool temporarily. When you're finished editing, release the R key, and the previous editing tool will be restored.

Switch to the Select Tool (when timeline or video preview has focus)	C	C
--	---	---

 Hold C to switch to the Select Tool temporarily. When you're finished selecting clips, release the C key, and the previous editing tool will be restored.

Switch to the Select Tool (when timeline or video preview has focus)	A	A
--	---	---

 Hold C to switch to the Select Tool temporarily. When you're finished selecting clips, release the C key, and the previous editing tool will be restored.

 When using Final Cut Pro shortcuts.

Switch to the Slip Tool (when timeline or video preview	P	P
---	---	---

Command	Windows Shortcut	macOS Shortcut
has focus)		
 Hold P to switch to the Slip Tool temporarily. When you're finished editing, release the P key, and the previous editing tool will be restored.		
Switch to the Split Trim Tool (when timeline or video preview has focus)	T	T
 Hold T to switch to the Split Trim Tool temporarily. When you're finished editing, release the T key, and the previous editing tool will be restored.		
Switch to the Fade Tool (when timeline or video preview has focus)	F	F
 Hold F to switch to the Fade Tool temporarily. When you're finished editing, release the F key, and the previous editing tool will be restored.		
Switch to the Envelope Tool (when timeline or video preview has focus)	V	V
 Hold V to switch to the Envelope Tool temporarily. When you're finished editing, release the V key, and the previous editing tool will be restored.		
Switch to the Edit Streams mode	Shift+E	Shift-E
 Press and hold Shift before dragging the end of the audio or video stream with the Edit Tool, Roll Trim Tool, or Envelope Tool to enable Edit Streams mode temporarily.		
Add a track above the selected track	Ctrl+Shift+N	Shift-⌘ -N
Add a title clip	Ctrl+T	⌘ -T
Add a title clip	Ctrl+T	Control-T
 When using Final Cut Pro shortcuts.		
Add a marker	M	M

Command	Windows Shortcut	macOS Shortcut
Select all clips	Ctrl+A	⌘ -A
Copy selected clips	Ctrl+C	⌘ -C
Cut selected clips	Ctrl+X	⌘ -X
Paste at cursor	Ctrl+V	⌘ -V
Delete selected clips	Delete	Delete
Split the selected clip at the cursor	S	S
Split the selected clip at the cursor	Ctrl+B	⌘ -B



When using Final Cut Pro shortcuts.

Move the cursor to the previous/next clip (when timeline has focus)	[]	[]
Zoom out fully (when timeline has focus)	0	0
Zoom in time until each video thumbnail represents one frame	Alt+0	Option-0
Zoom in/out (when timeline has focus)	Up Arrow Down Arrow	Up Arrow Down Arrow
Zoom in/out (when timeline has focus)	Ctrl+=	⌘ -=
	Ctrl+-	⌘ --



When using Final Cut Pro shortcuts.

Zoom in/out (when timeline has focus)	Ctrl+Mouse Wheel Up/Down	⌘ -Mouse Wheel Up/Down
	Alt+Mouse Wheel Left/Right	Option-Mouse Wheel Left/Right
Increase/decrease track height (when timeline has focus)	Ctrl+Shift+Up Arrow	⌘ -Shift-Up Arrow
	Ctrl+Shift+Down Arrow	⌘ -Shift-Down Arrow
Increase/decrease track height (when timeline has focus)	Ctrl+Shift+=	⌘ -Shift-=
	Ctrl+Shift+-	⌘ -Shift--



When using Final Cut Pro shortcuts.

Command	Windows Shortcut	macOS Shortcut
Scroll vertically	Mouse Wheel Up/Down	Mouse Wheel Up/Down
Scroll horizontally	Shift+Mouse Wheel Up/Down	Shift+Mouse Wheel Up/Down
	Mouse Wheel Left/Right	Mouse Wheel Left/Right
Toggle snapping	F8	F8
Toggle snapping	N	N
 When using Final Cut Pro shortcuts.		
Toggle snapping to all clips	Ctrl+Shift+F8	Shift-⌘ -F8

Gestures

Media Browser pane

Gesture	Result
Tap	Selects and loads a file.
Double-tap	Opens a file in the Video pane.
One-finger drag (touchscreen)	Scrolls the list vertically.
Two-finger drag (trackpad)	
One-finger flick (touchscreen)	Scrolls the list with inertia.
Two-finger flick (trackpad)	

Timeline

Gesture	Result
Tap	Selects clips or sets the cursor position.
⌘ -One-finger vertical drag (Magic Mouse- macOS only)	Zooms the timeline horizontally.
⌘ -Two-finger vertical drag (Magic Trackpad - macOS only)	
Two-finger vertical drag (trackpad)	Scrolls the timeline vertically.
Single-finger left/right swipe (Magic Mouse - macOS only)	Scrolls the timeline horizontally.
Two-finger left/right swipe (Magic Trackpad - macOS only)	
Single-finger clip drag on trackpad (Windows 8)	Moves clip.
Three-finger clip drag on trackpad (macOS only)	
Single-finger timeline or cursor drag	Scrub timeline.

Gesture	Result
on trackpad (Windows 8)	
Three-finger cursor drag (Magic Trackpad - macOS only)	

.

.aaf interchange 23
.fcpxml interchange 24
.prproj interchange 23
.txt interchange 24

3

3 dB notch pan type 88

6

6 dB notch pan type 89

A

add as tracks 75
add color gradient 146-147
Add control point 148
add envelope points 124
add marker 118
Add pan type 88
add text 141
add to timeline 60
adding keyframes 155
adding tracks 75
adjust envelope 125
Adobe Premiere 21
aspect ratio 14
ASR 122
audio-only clips 129
audio-only render 20
audio device 169
audio meters 167
audio mode 131
automatic fade 66, 102, 108
autosave project 11
Avid Media Composer 21

B

background color 143, 148
backup project files 11
Best match 20
blank track 75
bold text 142
bypass video effects 69

C

Catalyst Prepare library 129
Catalyst Prepare storyboard 28
changing a marker's color 118
channel count 15
channel mapping 20
channel setup 15
CinemaScope overlay 70
clip
 audio stretch 131
 contained 101
 cropping 111
 crossfade 101
 deleting 114
 end 130
 fade in length 130
 fade out length 130
 fades 122
 gain 131
 level 122
 media 128
 name 128
 opacity 122, 131
 properties 128
 rate 131
 roll trim 104
 select 98, 127
 slip 109
 slip trimming 104, 110

- snapping 115
- source offset 130
- split trim 103
- splitting 108
- start 130
- trim 102
- volume 131, 142
- clip effects 132, 135
- clip fade 123
- clip folder 129
- Clip Inspector 128
- clip level 122
- clip library 129
- clip lists 119
- clip opacity 122
- clip streams 129
- clip volume 122
- color gradient 147
- color gradient angle 148
- color gradient center 147
- color gradient type 147
- compositing 77, 150
- Constant power pan type 88
- contained clips 101
- continuous playback 73
- copying clips 113
- creating a nested timeline 120
- creating clips 60
- creating color-gradient clips 147
- creating projects 11
- creating solid-color clips 146
- creating title clips 141
- cropping clips 111
- crossfading clips 101
- cursor position 99
- custom sample rate 15
- customizing keyboard shortcuts 170
- cutting clips 113

D

- deleting clips 114

- deleting keyframes 156
- deleting markers 118
- deleting tracks 76
- display CinemaScope overlay 70
- display mode 28
- display secondary window 170

E

- edit clip effects 132
- edit color gradient 147
- edit picture in picture 77, 150
- edit solid color 147
- edit text 132, 142
- edit timeline effects 16
- edit track effects 92
- editing tools 95
- editingkeyframes 156
- effects
 - clip 132
 - timeline 16
 - track 92
- empty track 75
- enable outline 146
- enable shadow 145
- end
 - clips 130
- envelope fade curves 126
- eraser mode 103
- exporting projects 21, 23
- external monitor device 170
- external monitor resolution 170

F

- fade curves 126
- fade in length
 - clips 130
- fade out length
 - clips 130
- file formats 31
- Final Cut Pro X 21, 24

- finalizing Professional Disc volumes 31
- finding media 27
- fit 67
- flip envelope 127
- folder
 - clips 129
- font 142
- formatting Professional Disc volumes 31
- formatting SxS 31
- frame rate 14
- freeze frame 131
- fx, applying to clips 135
- fx, applying to the timeline 139
- fx, applying to tracks 137

G

- gain
 - clips 131
 - master output 15
- gestures 181
- Go to End 68
- Go to Start 68
- GPU acceleration 169
- grade in 15
- gradient angle 148
- gradient center 147
- gradient type 147
- grading color space 15
- graticule 71

H

- height 14
- histogram monitor 70
- horizontal alignment 143

I

- image sequence 20
- import from storyboard 28
- import library 28

- Inspector
 - Clip tab 128
 - Timeline tab 14
 - Track tab 86
- interactive overlay for video effects 72
- italic text 142

J

- J cut 106
- JKL shuttle 72

K

- keyboard shortcuts 170-171
- keyframe animation 155
- keyframes
 - adding 155
 - deleting 156
 - editing 156
 - moving 156

L

- L cut 106
- layering clips 77, 150
- length
 - clips 130
- level 122
- library
 - clips 129
 - importing 28
 - properties 129
- list view 28
- loop playback 73
- Loop Playback 68
- lower third 143

M

- magnification 60, 103, 107
- magnifying glass 67

- mark in 30
- mark out 30
- markers 118
 - color 118
 - position
 - position 118
 - ruler 93, 119
- mask to 2.39
 - 1 70
- match timeline aspect 111
- matching audio channels 16, 132
- media 128
- Media Browser pane 27
- Media Composer 23
- meters 167
- microfade 66, 102, 108
- missing media 13
- monitor resolution 170
- move marker 118
- moving clips 99
- moving keyframes 156
- moving tracks 76
- multichannel audio 158
- multiple clip selection 98
- mute
 - channel 91
 - master output 15
 - tracks 84, 89

N

- name clip 128
- name marker 118
- navigating the timeline 72
- nested timelines 119
- new library 63
- New Project 11
- Next Frame 68
- number of channels 15

O

- offline media 13
- opacity 122
 - clips 131
- open library 28
- Open Project 11
- opening a nested timeline 120
- opening projects 11
- outline color 146
- outline thickness 146
- output aspect 111
- overlay for video effects 72

P

- pan tracks 85, 87
- pan type
 - channel 90
 - tracks 88
- parameter keyframes 155
- pasting clips 82, 113
- picture-in-picture effect 77, 150
- pixel aspect ratio 14
- Play 68
- playing media 65
- position interact 17, 71, 92, 133, 137, 139-140
- position, text 142
- positioning clips 77, 150
- positioning the cursor 99
- Premiere Pro CS6 21, 23
- preview clip 29
- Previous Frame 68
- primary display 170
- .creditprj files
 - creating 11
 - opening 11
 - properties 14
 - saving 13
- Professional Disc format 31
- project audio meter 167

- project backup 11
- projects
 - creating 11
 - opening 11
 - properties 14
 - saving 13
- proxy editing 13
- punch-in clips 101

Q

- quantize to frames 115, 117
- quick fade (audio) 66, 102, 108

R

- range selection 98
- rate
 - clips 131
- rearranging tracks 76
- refresh properties 128
- relinking project media 13
- Remove control point 148
- removing keyframes 156
- rename marker 118
- render audio 20
- render image sequence 20
- rendering multichannel audio 20
- rendering projects 20
- replace media 13, 127
- Reset mark in/out points 74
- ripple edits 114
- ripple sync 86, 115
- roll trim 104
- rotation 143
- ruler format 14

S

- safe areas 70
- sample rate 15
- Save Project 13

- Save Project As 13
- saving projects 13
- scroll timeline 72
- scrub control 72
- secondary window 170
- select marker 118
- selecting clips 98
- Set to default 125
- Set to max 125
- Set to min 125
- shadow color 145, 148
- sharing clips 18
- sharing files with YouTube 18
- shortcuts 171
- Show in Explorer 28
- Show in Finder 28
- show safe areas 70
- show/hide marker ruler 119
- shuttle control 72
- slip 109, 130
- slip trim 104, 110
- snapping
 - clips 115
 - quantize to frames 117
- solid color 146
- solo
 - channel 91
 - tracks 84, 89
- sound device 169
- source offset
 - clip 130
- spanned clips, adding to timeline 62
- split-screen preview 66, 69, 102, 109
- split trim 103
- splitting clips 108
- spring-loaded shortcuts 95, 177
- start
 - clips 130
- Stop 68
- storyboard 28
- storyboards 119
- stream editing 106

- streams 129
- stretch audio 131
- supported formats 31
- SxS format 31

T

text

- clips 141-142
- color 143
- font 142
- generator 132
- position 142
- rotation 143
- size 142
- thumbnail view 28
- timeline aspect 111
- timeline audio meter 167
- timeline effects 16, 139
- Timeline Inspector 14
- timeline nesting 119
- timeline properties 14
- timeline settings 92-93, 119
- title clips 141
- tools 95
- touchscreen navigation 181
- track audio settings 88, 90
- track effects 92, 137
- Track Inspector 86
- trackpad navigation 181
- tracks
 - adding 75
 - adjusting controls 82
 - audio meter 168
 - deleting 76
 - height 93, 119
 - moving 76
 - order 76
 - properties 86
 - volume 83
- transport controls 68
- trim adjacent 104

- trim clip end 102
- trim clip start 102

U

- uploading to Ci 28
- uploading to YouTube 18

V

- vectorscope monitor 71
- Vegas Pro EDL 21, 24
- vertical alignment 143
- video-only clips 129
- video effect animation 155
- video effects 135
- video generators 141
- Video pane 65
- video preview 170
- video preview overlay 72
- video preview position control point 17, 71, 92, 133, 137, 139-140
- video processing device 169
- video transitions 149
- volume
 - clips 131
 - master output 15
 - tracks 87, 89
- volume, automating 123
- volume, automating | Default.Monaco | [4] 120

W

- waveform monitor 70
- width 14

X

- XDCAM Professional Disc format 31

Y

YouTube 18

Z

zoom timeline 60, 62, 103, 107

